

# EVE-NG Professional Cookbook

Version 4.5

Author: Uldis Dzerkals

Editors: Michael Doe Christopher Lim

#### © EVE-NG LTD

The information contained in this document is the property of EVE-NG Limited

The contents of the document must not be reproduced or disclosed wholly or in part or used for purposes other than that for which it is supplied without the prior written permission of EVE-NG Limited.



# **Table of Contents**

P	REFACE		9
1	INTROD	UCTION	10
	1.1 WH	AT IS EVE-NG?	10
		AT IS EVE-NG USED FOR?	
		o is EVE-NG for?	
2	SYSTEM	/ REQUIREMENTS	11
	2.1 HAR	DWARE REQUIREMENTS	11
	2.1.1	Minimal Laptop/PC Desktop system requirements	11
	2.1.2	Recommended Laptop/PC Desktop system requirements	
	2.1.3	Virtual Server system requirements	
	2.1.4	Dedicated Server (bare) system requirements	
	2.1.5	Nodes per lab calculator	
		PORTED VIRTUALIZATION PLATFORMS AND SOFTWARE	
	2.3 Uns	SUPPORTED HARDWARE AND SYSTEMS	14
3	INSTAL	LATION	15
	3.1 VM\	NARE WORKSTATION OR VM PLAYER	15
	3.1.1	VMware workstation EVE VM installation using ISO image (preferred)	
	3.1.1.1	EVE VM Setup and Settings	
	3.1.1.2	EVE-NG VM Installation steps	18
	3.1.2	VMware workstation OVF deployment	
	3.1.2.1	Deployment and VM machine settings	
	3.1.2.2	OVF VM update to the latest EVE version	
	3.1.2.3	OVF VM HDD Size expansion	
		NARE ESXI	
	3.2.1	VMware ESXi EVE installation using ISO image (preferred)	
	3.2.1.1	EVE-NG ESXi VM Setup and Settings	
	3.2.1.2 3.2.2	EVE-NG ESXi VM Installation steps	
	3.2.2.1	ESXi OVF VM Setup and Settings	
	3.2.2.2	, e	
	3.2.2.3		
		E HARDWARE SERVER EVE INSTALLATION	
	3.3.1	Ubuntu Server Installation Phase 1	
	3.3.2	EVE Professional Installation Phase 2	
	3.4 God	OGLE CLOUD PLATFORM	42
	3.4.1	Google account	42
	3.4.2	Goggle Cloud project	42
	3.4.3	Preparing Ubuntu boot disk template	44
	3.4.4	Creating VM	
	<i>3.4.5</i>	EVE-NG-PRO installation	
	3.4.6	Access to Google Cloud EVE-PRO	
	<i>3.4.7</i>	Optional: GCP Firewall rules for native console use	49
		MANAGEMENT IP ADDRESS SETUP	
	3.5.1	Management static IP address setup (preferred)	
	3.5.2	EVE Management IP address setup via DHCP	
	3.5.3	Internet proxy setup	
	3.5.4	EVE Management IP address reset	
		IVE TELNET CONSOLE MANAGEMENT SETUP	
	3.6.1	Windows Native Console	
	3.6.2	Linux Native Console	
	3.6.3	MAC OSX Native Console	
	o./ LOG	IN TO THE EVE WEB GUI	b()



4 EVE-N	NG PROFESSIONAL LICENSING	61
4.1 E	VE-NG PROFESSIONAL BASE LICENSE	61
4.2 E	VE-NG LEARNING CENTRE LICENSES	62
	VE-NG CORPORATE LICENSES	
	SER ROLES COMPARISON CHART	
	CENSE PURCHASING AND ACTIVATION	
	CENSE DEACTIVATION	
	CENSE REHOSTING.	
5 EVE-I	NG PROFESSIONAL UPDATE & UPGRADE	69
5.1 E	VE-NG PROFESSIONAL UPDATE	69
	VE-NG PROFESSIONAL UPGRADE	
6 TYPE	S OF EVE MANAGEMENT CONSOLES	
6.1 N	ATIVE CONSOLE	72
6.1.1	Native Console: telnet	
6.1.2	Native Console: Wireshark	
6.1.3	Native Console: VNC	
6.1.4	Native Console: RDP	
-	TML5 CONSOLE	
6.2.1	HTML5 Console window functions	
6.2.2	HTML5 Console: Telnet	
6.2.3	HTML5 Console: Veinet	
6.2.4	HTML5 Console: VNC	
6.2.5	HTML5 Console: RDP	
	TML5 DESKTOP CONSOLE	
6.3.1	Login to HTML5 Desktop console	
6.3.2	HTML5 Desktop Console: telnet	
6.3.3	HTML5 Desktop Console: Wireshark	
6.3.4	HTML5 Desktop Console: RDP	
6.3.5	HTML5 Desktop Console: ThinClient Files exchange	83
6.3.5 7 EVE V	HTML5 Desktop Console: ThinClient Files exchange  VEB GUI MANAGEMENT	83 <b>84</b>
6.3.5 <b>7 EVE V</b> 7.1 E	HTML5 Desktop Console: ThinClient Files exchange  VEB GUI MANAGEMENT  VE MANAGEMENT PAGE	83 <b>84</b> 84
6.3.5 <b>7 EVE V</b> 7.1 E 7.1.1	HTML5 Desktop Console: ThinClient Files exchange  VEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons	
6.3.5 <b>7 EVE V</b> 7.1 E  7.1.1  7.1.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs	
6.3.5 <b>7 EVE V</b> 7.1 E  7.1.1  7.1.2  7.2 F	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT	
6.3.5 <b>7 EVE V</b> 7.1 E  7.1.1  7.1.2	HTML5 Desktop Console: ThinClient Files exchange  VEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1	HTML5 Desktop Console: ThinClient Files exchange  VEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs.  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE.  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  8 Import Folder	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.2  7.2.2  7.2.2  7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  8 Import Folder  Lab files Management  Lab files Management	
6.3.5  7 EVE V  7.1 E  7.1.1  7.1.2  7.2 F  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.1  7.2.2  7.2.2  7.2.2  7.2.2  7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  8 Import Folder  Lab files Management  1 Create Lab	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2  7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  Lab files Management  Lab files Management  1 Create Lab  2 Delete Lab	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2  7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs.  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  8 Import Folder  Lab files Management  1 Create Lab  2 Delete Lab  3 Clone Lab	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2  7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2 7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2  7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2 7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.3.2 7.3.8	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  6 Move Folder  7 Export Folder  8 Import Folder  Lab files Management  1 Create Lab  2 Delete Lab  3 Clone Lab  4 Move Lab  5 Export Lab  6 Import Labs  VE MANAGEMENT DROPDOWN MENU	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2 7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.3 E 7.3.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2 7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.3 E 7.3.1 7.3.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE	
6.3.5  7 EVE V  7.1 E 7.1.1 7.1.2 7.2 F 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.1 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.2.2 7.3 E 7.3.1	WEB GUI MANAGEMENT  VE MANAGEMENT PAGE  Management buttons  Management tabs  OLDERS AND LAB FILES MANAGEMENT  Folders Management  1 Default folder Running  2 Default folder Shared  3 Default folder Users  4 Create folder  5 Delete folder  8 Import Folder  8 Import Folder  Lab files Management  1 Create Lab  2 Delete Lab  3 Clone Lab  4 Move Lab  5 Export Lab  6 Import Labs  VE MANAGEMENT DROPDOWN MENU  EVE User management  1 Creating a new EVE User  2 Edit EVE User	83 84 84 85 86 86 86 87 88 88 89 90 91 91 91 91 92 93 93



7.3.1.5	User role sticky lab	
7.3.2	EVE Node management	101
7.3.2.1	Node management actions	
7.3.2.2	Node management filtering function	
7.3.3	EVE Lab management	
7.3.3.1	Lab management actions	103
	SYSTEM DROPDOWN MENU	
7.4.1	System Settings	104
7.4.2	Cluster Management	105
7.4.3	System status	105
7.4.4	System logs	106
7.4.5	Stop All Nodes	107
7.5 EVE	INFORMATION DROPDOWN MENU	107
7.6 EVE	LICENSING DROPDOWN MENU	107
7.7 Отн	ER TAB LINE INFO	108
7.8 LAB	PREVIEW AND GLOBAL SETTINGS	108
7.8.1	Lab preview window	108
7.8.2	Lab preview buttons	
7.8.3	Lab preview information	
7.8.4	Lab Global Settings	
	-	
8 EVE WE	B TOPOLOGY PAGE	111
8.1 SIDE	BAR FUNCTIONS	111
8.1.1	Add an object	
8.1.1.1	Node object	
8.1.1.2	Network object	
8.1.1.3	Picture object	
8.1.1.4	Custom shape object	
8.1.1.5	Text object	
8.1.1.6	Line object	
8.1.2	Nodes	
8.1.3	Networks	
8.1.4	Startup-configs	
8.1.5	Logical Maps	
8.1.6	Configured Objects	
8.1.7	More actions	
8.1.7.1	Start all nodes	
8.1.7.2	Stop all nodes	
8.1.7.3	Wipe all nodes	
8.1.7.4		119
8.1.7.5	Export all CFGs	119
8.1.7.6	Edit lab	
8.1.7.7	Topology screenshot	
8.1.7.8	Set node's startup-cfg to default configset	
8.1.7.9	Set node's startup-cfg to none	
8.1.7.10		
8.1.8	Refresh Topology	
8.1.9	Lab page zoom/unzoom	
8.1.10	Status	
8.1.11	Lab details	
8.1.12	Lab Tasks	
8.1.13	Lab Chat	
8.1.14	Lock Lab with password	
8.1.15	Fullscreen	
8.1.16	Hide interface labels	
8.1.17	Dark mode or Light mode	122
8.1.18	Close lab	
8.1.19	Logout	
		123



8.2.1	Lab topology menu	
8.2.2	Connection menu	
8.2.3	Cloud or Bridge network menu	
<i>8.2.4</i>	Stopped node menu	
8.2.5	Running node menu	
8.2.6	Selected nodes menu and features	
	E LAB NODE STATES AND SYMBOLS	
8.3.1	Stopped (non-running) nodes	
8.3.2	Running nodes	
8.3.3	Node connector symbol	
	ER	
8.4.1	Notifications area	
	NG WITH EVE LABS	
	EATING A LAB	
9.1.1	Adding nodes to the lab	
9.1.1.1		
9.1.2	Edit node	
9.1.2.1		
9.1.2.2		
9.1.3	Wipe Node	
9.1.4	Interconnecting nodes	
9.1.5	Edit connection link style	
9.1.6 9.1.7	Edit connection link quality	
9.1.7 9.1.8	Delete connection between nodes	
9.1.8 9.1.9	Delete Node	
	NNING LABS	
9.2 Kui	Starting lab	
9.2.1 9.2.2	Interconnecting running nodes (hotlinks)	
9.2.2	Link quality delay, packet loss, jitter and rate feature	143
	/ING LABS	
	PPPING LABS	
	RT SAVED LAB.	
	RKING WITH MULTIPLE RUNNING LABS	
	ORTING LABS	
	PORTING LABS	
	ETING LABS	
	OVING LABS	
	CLOUDS AND NETWORKS	
	RIDGE NETWORK	
-	JTERNAL NETWORK	_
	PRIVATE NETWORK	•
	IAT NETWORK	
	THER CLOUD INTERFACES	
	CONNECTING EXTERNAL VM MACHINES TO THE EVE LAB	
	ESXi VM machines	
	VMWare workstation machines	
	CONNECTING EVE LAB TO A PHYSICAL DEVICE	
	ESXI EVE	
	VMWare workstation EVE	_
	Bare metal server EVE	
11 ADVA	NCED EVE LAB FEATURES	161
11.1 L	AB DESIGN OBJECTS	161
11.1.1	Custom shape	161



11.1.2	Resize square or circle objects	
11.1.3	Text	
11.1.4	Add picture to the topology	163
11.1.5	Custom object linking with telnet or other protocol	164
11.1.6	Line object	
11.1.7	Nodes connection links design	
11.1.8	Cloning objects and overlay positions	
11.1.9	Objects EditingLock objects movement	167
	CUSTOM DESIGN LOGICAL TOPOLOGY	
11.2.1		
11.2.2		
11.2.3	Delete topology or mapping	
	MULTI-CONFIGURATION SETS EXPORT FEATURE	
11.3.1	Supported nodes for configuration exports	
11.3.2	Startup config management	
11.3.2		
11.3.2		
11.3.2	3 Multiple selected nodes commands	.173
11.3.2	O	
11.3.2	1 6	
11.3.3	Export Default configuration set	
11.3.4	Boot nodes from exported Default config set	
11.3.5	Export new custom config set	
11.3.6	Edit exported configurations	
11.3.7	Set lab to boot from config set	
11.3.8	Set lab to boot from none	
11.3.9	Delete a config set	
11.3.10		
11.3.11	, ,	
11.3.12	, ,	
11.3.13		
11.3.14	, ,	
11.3.15 11.3.16	5	
	AB TIMER	
11.4 L	Set the Lab Countdown Timer	
	Stop the Lab Countdown Timer	
	AB TASKS	
11.5.1	Creating a new simple task	
11.5.1	Edit a simple task	
11.5.3	Create a multi tabs task (task on multiple tabs/pages)	
11.5.4	Edit a multi tabs task (task on multiple tabs/pages)	
11.5.5	Edit tabs (Multi tabbed task).	
11.5.6	Create a task with your PDF workbook	
11.5.7	Create a task with Online document (PDF or HTML)	
11.5.8	Delete a task	
12 WIRE	SHARK CAPTURE	189
12.1 N	NATIVE CONSOLE WIRESHARK CAPTURING	189
	HTML5 CONSOLE WIRESHARK CAPTURING	
12.3 F	HTML5 DESKTOP CONSOLE WIRESHARK CAPTURING	193
	CLIENT FILE EXCHANGE	
	HINCLIENT FILES DOWNLOADING	
	HINCLIENT FILE UPLOAD	
13.3	OTHER THINCLIENT FILE OPERATIONS	198
14 DOC	KERS	202



	14.1	EVE INTEGRATED DOCKER STATIONS	202
	14.1.1	Docker Machines	202
	14.1.2	Docker DHCP IP address setup	204
	14.1.3	Docker Static IP address setup	205
	14.1.4		
	14.1.5		
		DOCKER CONSOLES	
	14.3	DOCKER CLI ROOT ACCESS	
	14.4	DOCKERS RE-INSTALL/UPDATE	
	14.5	EXTRA DOCKER PACKAGES	
	14.6	THIRD PARTIES DOCKERS	
	14.6.1	,	
	14.6.2		
		CUSTOMIZE DOCKER IMAGE WITH YOUR OWN CHANGES.	
	14.8	DELETE DOCKER IMAGE FROM EVE	215
15	EVE	CLUSTER SYSTEM	217
13		CLUSTER STSTEM	211
	15.1	EVE CLUSTER DESIGN MODELS	217
	15.1.1	Bare metal servers cluster	217
	15.1.2		
	15.1.3		
	15.1.4		218
	15.1.5		
		EVE CLUSTER PRE-REQUISITES	
	15.2.1		
		EVE CLUSTER MEMBER'S HARDWARE REQUIREMENTS	
	15.4	EVE CLUSTER MASTER NODE INSTALLATION	
		ESXI EVE SATELLITE VM INSTALLATION	
		EVE-NG Satellite ESXi VM Setup and Settings	
	15.5.2	EVE-NG Satellite ESXi VM Installation steps	
	15.6	BARE METAL SERVER EVE SATELLITE INSTALLATION	227
	15.6.1	Ubuntu Server Installation Phase 1	227
	15.6.2	EVE Satellite Installation Phase 2	232
	15.7	GOOGLE CLOUD EVE SATELLITE INSTALLATION	233
	15.7.1		
	15.7.2	· · ·	
	15.7.3	<u> </u>	
	15.7.4		
	15.8	CLUSTER MANAGEMENT	
		Join Satellite nodes to the Master	233
	15.8.1		
	15.8.2		
	15.8.3	, , , , , , , , , , , , , , , , , , , ,	
	15.8.4	<b>o</b>	
		CREATING EVE LABS IN CLUSTER	
	15.9.1		
	15.10	CLUSTER SYSTEM MONITORING	
	15.10.	1 Cluster Monitoring page	242
	15.10.	2 Satellite disaster recovery	243
	15.10.	3 EVE Cluster Status	243
	15.10.		
	15.11	CLUSTER SYSTEM UPGRADE	
16	EVE	TROUBLESHOOTING	246
	16.1	CLI DIAGNOSTIC INFORMATION DISPLAY COMMANDS	216
	16.1.1		
	_	-17	
	16.1.2		
	16.1.3	, ,	
	16.1.4	Display EVEs CPU INFO:	246



16.1.5 Display EVEs CPU manufacturer:	246
16.1.6 Display EVEs HDD utilization	
16.1.7 Display EVEs Bridge interface status	
16.1.8 Display EVEs system services status	
16.2 EXPAND EVES SYSTEM HDD	247
16.2.1 HDD space alert	
16.2.2 Expand HDD on VMware Workstation	248
16.2.3 Expand your HDD on ESXi	
16.2.4 Expand your HDD on a Bare Metal EVE Server	249
16.3 RESET MANAGEMENT IP	
16.4 EVE PRO SQL DATABASE RECOVERY	
16.5 EVE PRO MIGRATION FROM HOST TO HOST	
16.6 EVE LOG FILES	250
16.7 EVE CLI DIAGNOSTIC INFO	250
17 EVE EXTRAS	252
17.1 EVE PRO RADIUS SERVER SETUP FOR USER AUTHENTICATION	
17.1.1 EVE User setup for Radius authentication	
17.2 LAB CHAT	
17.3 CUSTOM MAC ADDRESS FOR NODE MANAGEMENT	
17.4 WINDOWS NODE SETTINGS FOR WIFI DONGLE	254
18 IMAGES FOR EVE	257
18.1 QEMU IMAGE NAMING TABLE	257
18.2 HOW TO PREPARE IMAGES FOR EVE	
18.3 HOW TO ADD CUSTOM IMAGE TEMPLATE	
18.3.1 Templates folder choice	
18.3.2 Prepare template file	
18.3.3 Prepare interface format and name lines	
18.3.4 Edit your new template file:	
18.3.5 Prepare new icon for your template:	
18.3.6 Template use	
18.4 How to hide unused images in the node list	
19 EVE RESOURCES	263



## **Preface**

When I first heard about EVE-NG I was skeptical. Back then I used to Lab mainly with ESX by deploying many virtual Devices and connecting them manually by separate vSwitches for Point-to-Point connections. The Problem with that was, that it was extremely time-consuming and did not scale - for every new Device I had to create multiple vSwitches to interconnect them with the virtual Machines - a Nightmare. I was in the middle of my JNCIE-Exam-Prep when I first saw EVE-NG on Twitter - I downloaded the Community Edition, which was the only Edition back then and I was amazed how easy Labbing all of a sudden was. No more deploying of vSwitches to interconnect nodes and boy did it Scale...

If you follow me on Twitter you know, that I'm one of the hardest Juniper Fanboys and of course my Goal was to "Juniperize" EVE. I started to get in touch with UD and Alain and found myself into the Position as one of the Juniper Test Guys. Meanwhile I added nearly all Juniper related Devices (including vSRX and JATP) and I still test a Lot - but now on EVE-Pro.

The Pro-Edition was a big step forward for the Project. It added some nice Features like "hot-add-interconnect" and the Ability to use EVE-NG with multiple Users. Especially Companies will love EVE as it is THE Solution for Labs and PoC's. I have successfully run over 30 PoC's in EVE and over 100 Labs (Job-Related and Personal Labs) - and I still enjoy it every day thanks to EVE and the amazing Team behind it. When the Guys asked me to write the Introduction I was of course honored and now this Book is finally coming out to help you on your Quest to Setup, Run and Manage EVE-NG in a lot of possible ways.

Well - enough from my Side. I hope you enjoy this Cookbook and use it wisely for your Everyday EVE Work. If you have Problems there is always the EVE-Forum and Live-Helpdesk - you will also find me there from time to time :)

I wish you happy reading and if you think, that this Product is amazing feel free to support it by buying the PRO-Edition or Donating a bit – it helps to expand this already cool Product even more and it also honors all the work that the Guys spent in it.

Christian Scholz @chsjuniper

© EVE-NG LTD Page 9 of 263



# 1 Introduction

#### 1.1 What is EVE-NG?

To describe what Emulated Virtual Environment – Next Generation (EVE-NG) is without solely stating dry facts about features, we need to elaborate more on what EVE-NG can be used for and whom it would be useful for.

In some trivial dry words, EVE-NG gives you tools to use around virtual devices and interconnect them with other virtual or physical devices. Many of its features greatly simplify the usabilities, re-usability, manageability, interconnectivity, distribution and therefore the ability to understand and share topologies, work, ideas, concepts or simply "labs". This can simply mean it will reduce the cost and time to set up what you need or it might enable you to do tasks you would not have thought could be done this simple.

#### 1.2 What is EVE-NG used for?

This is the real question but there is no finite answer, the possibilities are almost limitless and depends on what you want to use it for.

It can be used for studying all kinds of technologies. You can learn about general technologies or vendor specific topics. You can test new technologies like network automation, SDN, etc. It can be used to recreate corporate networks and test changes before putting them into production. You can create proof of concepts for clients. You can troubleshoot network issues by recreating them and e.g. use Wireshark to inspect packets.

It is most definitely not just for networking, it can be used to test software in simulated networks, test out security vulnerabilities of any kind, system engineering like LDAP and AD servers and many more areas.

You could set it up to automate sandboxing unknown files/software and use software to analyse short and long term behaviour for malicious intent much simpler than without EVE-NG.

The list of what EVE-NG can be used for could go on indefinitely, possibilities are limited by knowledge and imagination only. Both of which can be improved with EVE-NG.

To get a very small idea of what can be done with EVE-NG, check out the tested/<u>supported images</u> (many have not been tested, almost everything virtual should run on EVE-NG) and refer to section 17.

EVE-NG helps you achieve what you want to and more.

#### 1.3 Who is EVE-NG for?

EVE-NG is for everyone working in the Information Technology Sector, period.

It is for very large enterprise companies, training facilities, service providers, consultants, people who want to train themselves; it is for everyone, it is for YOU!

Use-cases that are more than worth it, almost priceless even, can be found everywhere.

The EVE-NG community version is free for everyone; while the paid professional version adds a few things that make your life easier. Almost everything can still be done with the free version, just less conveniently and therefore more time-consuming.

However, with the free version, the possibility to train yourself with technologies, hone your skills and become an expert even with very no monetary possibilities. For some this is and has been life changing.

© EVE-NG LTD Page 10 of 263



# 2 System requirements

EVE-NG is available in the OVF or ISO file format. The Open Virtualization Format (OVF) is an open standard for packaging and distributing virtual appliances. It can be used to deploy a VM in hypervisors like VMware Workstation, Player and ESXi. Please note that installing EVE as a Virtual Machine (VM) will mean any nodes deployed within EVE will be nested. Nested virtualization causes degraded performance in deployed nodes. This should be fine for lab purposes as long as the host meets or exceeds the resource requirements for the deployed nodes.

EVE-NG can also be installed directly on physical hardware, without a hypervisor, using the provided ISO image. This is referred to as a "bare metal" install and is the most recommended method of installing EVE-NG.

## 2.1 Hardware requirements

#### 2.1.1 Minimal Laptop/PC Desktop system requirements

#### Prerequisites:

CPU: Intel CPU supporting Intel® VT-x /EPT virtualization Operating System: Windows 7, 8, 10 or Linux Desktop VMware Workstation 14.0 or later VMware Player 14.0 or later

PC/Laptop HW requirements	
CPU	Intel i5/i7 (4 Logical processors), Enabled Intel virtualization in BIOS
RAM	8Gb
HDD Space	50Gb
Network	LAN/WLAN
EVE Virtual machine requirements	
CPU	4/1 (Number of processors/Number of cores per processor) Enabled Intel VT-x/EPT virtualization engine
RAM	6Gb or more
HDD	50Gb or more
Network	VMware NAT or Bridged network adapter

Note: Minimal PC Desktop/Laptop will be able to run small Labs. The performance and quantity of nodes per lab depend on the types of nodes deployed in the lab.

#### Example:

IOL image-based nodes: up to 40-50 nodes per lab Dynamips image-based nodes: up to 20-25 nodes per lab vIOS image-based nodes: up to 8-10 nodes per lab CSRv1000 or XRv image-based nodes: up to 2-3 per lab

© EVE-NG LTD Page 11 of 263



#### 2.1.2 Recommended Laptop/PC Desktop system requirements

#### **Prerequisites:**

CPU: Intel CPU supporting Intel® VT-x /EPT virtualization Operation System: Windows 7, 8, 10 or Linux Desktop VMware Workstation 14.0 or later VW Ware Player 14.0 or later

PC/Laptop HW requirements		
CPU	Intel i7 (8 Logical processors), Enabled Intel virtualization in BIOS	
RAM	32Gb	
HDD Space	200Gb	
Network	LAN/WLAN	
	EVE Virtual machine requirements	
CPU	8/1 (Number of processors/Number of cores per processor) Enabled Intel VT-x/EPT virtualization engine	
RAM	24Gb or more	
HDD	200Gb or more	
Network	VMware NAT or Bridged network adapter	

Note: PC Desktops/Laptops will be able to run small to medium Labs. Performance and quantity of nodes per lab depend on the type of nodes deployed in the lab.

#### Example:

IOL image-based nodes: up to 120 nodes per lab vIOS image-based nodes: up to 20-40 nodes per lab

CSR image-based nodes: up to 10 per lab

#### 2.1.3 Virtual Server system requirements

#### **Prerequisites:**

CPU: Intel Xeon CPU supporting Intel® VT-x with Extended Page Tables (EPT) Operation System: ESXi 6.0 or later

Server HW requirements	
CPU	Recommended CPU 2x Intel E5-2650v3 (40 Logical processors) or better supporting Intel® VT-x with Extended Page Tables (EPT)  Minimum CPU is any Intel Xeon CPU supporting Intel® VT-x with Extended Page Tables (EPT)
RAM	128Gb
HDD Space	2Tb
Network	LAN Ethernet
EVE Virtual machine requirements	
CPU	32/1 (Number of processors/Number of cores per processor) Enabled Intel VT-x/EPT virtualization engine
RAM	64Gb or more
HDD	800Gb or more

© EVE-NG LTD Page 12 of 263



Network vSwitch/VMnet	
-----------------------	--

Note: Performance and quantity of nodes per lab depends from the type of nodes used in the lab.

Example:

120 IOL image-based lab 20 CSRv1000 image-based nodes per lab

#### 2.1.4 Dedicated Server (bare) system requirements

#### **Prerequisites:**

CPU: Intel Xeon CPU supporting Intel® VT-x with Extended Page Tables (EPT) Operation System: Ubuntu Server 18.04 LTS x64

Server HW requirements	
CPU	Recommended CPU Intel E5-2650v3 (40 Logical processors) or better supporting Intel® VT-x with Extended Page Tables (EPT) Minimum CPU is any Intel Xeon CPU supporting Intel® VT-x with Extended Page Tables (EPT)
RAM	128Gb
HDD Space	2Tb
Network	LAN Ethernet

Note: Performance and quantity of nodes per lab depends from type of nodes used in the lab.

#### 2.1.5 Nodes per lab calculator

It is recommended to use the "nodes per lab calculator" to achieve best performance and avoid overloading your EVE system.

https://docs.google.com/spreadsheets/d/1Rbu7KDNSNuWiv\_AphWx0vCek8CKVB1WI/edit#gid=2010030751

# 2.2 Supported virtualization platforms and software

- VMware Workstation 14.0 or later
- VMware Player 14.0 or later
- VMware ESXi 6.0 or later
- Ubuntu Server 18.04 LTS as platform for bare metal
- Google Cloud Platform
- AMD CPU based PC or Server (the Newest AMD CPU versions are supported)

© EVE-NG LTD Page 13 of 263



# 2.3 Unsupported hardware and systems

### The following are currently not supported officially:

- VirtualBox virtualization
- Citrix XenServer
- Microsoft HyperV
- Ubuntu 20.x
- Proxmox

© EVE-NG LTD Page 14 of 263



# 3 Installation


# 3.1 VMware Workstation or VM Player

# 3.1.1 VMware workstation EVE VM installation using ISO image (preferred)

Mandatory Prerequisites: Internet must be reachable from your PC and VMware. EVE ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must work as well, to check it, do a named ping, for example ping www.google.com

Download EVE-NG Professional ISO distribution image: https://www.eve-ng.net/index.php/download/


#### 3.1.1.1 EVE VM Setup and Settings



© EVE-NG LTD Page 15 of 263



Step 3: Select a Guest Operating system: Step 4: Enter the name for your EVE-PRO Linux and select the version: Ubuntu 64-bit VM and select Location where your EVE VM will be stored on the host PC. New Virtual Machine Wizard New Virtual Machine Wizard × Select a Guest Operating System Which operating system will be installed on this virtual machine? Name the Virtual Machine What name would you like to use for this virtual machine? Guest operating system Microsoft Windows Virtual machine name: Linux EVE-PRO Novell NetWare
Solaris Other Location: G:\EVE\_PRO-VM Browse... The default location can be changed at Edit > Preferences. Version Ubuntu 64-bit Help < Back Next > Cancel < Back Next > Cancel




Step 7: Assign desirable memory

Step 8: Set Processors "Number of processors" and "Number of cores per


© EVE-NG LTD Page 16 of 263






Step 9a: Select your desirable Network Adapter. **Laptop PC** 

NOTE: It is recommended to choose the NAT adapter option for Laptops to avoid EVE management interface IP changes. This can happen anytime the laptop is connected to a different SSID



Step 9b: Select your desirable Network Adapter. **Desktop PC** 

NOTE: Desktop PC EVE management interface can be either NAT or Bridged to home LAN subnet.




Step 10: Select CD/DVD Option: "use ISO image file." Browse to your downloaded

Step 11: Confirm VM Settings.

© EVE-NG LTD Page 17 of 263






#### 3.1.1.2 EVE-NG VM Installation steps

Mandatory Prerequisites: Internet must be reachable from your PC and VMware. EVE ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must work as well, to check it, do a named ping, for example ping www.google.com

#### **EVE VM Installation from ISO has 3 Phases**

#### Phase 1 (Ubuntu installation)



Step 2: Be sure that "Install EVE PRO VM" is highlighted. Confirm with Enter.




Step 3: Make sure that English is selected and confirm with Enter.


Step 4: You can select your own Location, or later, after management IP assignment,

© EVE-NG LTD Page 18 of 263







location will be set automatically. You can leave United States. Confirm with Enter.



Step 5: **DHCP ENABLED**, EVEs hostname by default is **eve-ng**. You can change it if you wish. Using the Tab key select continue and confirm with Enter. Continue to **Step 14** 



Step 6: **DHCP DISABLED**/Static IP setup. If you have not enabled DHCP in the network, you must assign an IP address manually. Confirm Continue with Enter.





Step 7: Confirm selection "Configure network manually" with Enter

Step 8: Enter your desirable EVE management IP, using the Tab key select "Continue" and confirm with Enter


© EVE-NG LTD Page 19 of 263







Step 9: Enter your subnet mask, using the Tab key select "Continue" and confirm with Enter




Step 10: Enter your Gateway IP, using the Tab key select "Continue" and confirm with Enter



Step 11: IMPORTANT. The name server must be able to resolve public DNS entries and will be used during the next install steps. Enter your name server IP, using the Tab key select "Continue" and confirm with Enter

Step 12: EVEs hostname by default is **eveng**. It can be changed if you wish, using the Tab key select continue and confirm with Enter



© EVE-NG LTD Page 20 of 263






Step 13: Enter your networks domain name. You are free to use anything you like, for example: eve-ng.net

Using the Tab key select continue and confirm with Enter



Step 14: If your DNS IP settings are correct, Ubuntu will detect your location automatically by connecting to Ubuntu servers. Confirm with Enter.




Step 15: Select Continue and confirm with Enter. If required, proxy settings can be configured later using EVE WEB GUI System/System Settings described in section 3.5.3

Step 16: Select no automatic updates and confirm with Enter. Security updates can later be run manually from EVE cli.

© EVE-NG LTD Page 21 of 263









#### EVE VM Installation Phase 2 (EVE installation)

Step 17: Continue with Enter, the EVE VM will reboot and finish the installation phase 2



Step 18: Once the EVE login screen appears, login to the CLI with root/eve and continue with installation phase 3



#### EVE VM Installation Phase 3 (Management IP setup and updates)

Step 19: Setup EVEs Management IP address. A Static IP address setup is preferred.

Follow steps in section:

3.5.1 for static IP, 3.5.2 for DHCP IP

Step 20: After your EVE is rebooted,

Login to EVE CLI and type:

apt update
apt upgrade

Follow steps in section: 5.1, 5.2

**NOTE:** Verify your EVE-NG server installation, type "dpkg -l eve-ng-pro" command, it must display latest EVE Pro version

```
root@eve-ng:~# dpkg -l eve-ng-pro
Desired=Unknown/Install/Remove/Purge/Hold
| Status=Not/Inst/Conf-files/Unpacked/halF-conf/Half-inst/trig-aWait/Trig-pend
|/ Err?=(none)/Reinst-required (Status, Err: uppercase=bad)
```

© EVE-NG LTD Page 22 of 263



**NOTE:** If your newly installed EVE-PRO shows nothing like above, you must check your internet reachability and verify DNS configuration on your EVE-PRO server.

```
root@eve-ng:~# ping www.google.com
PING www.google.com (172.217.22.164) 56(84) bytes of data.
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=1
ttl=120 time=8.84 ms
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=2
ttl=120 time=8.84 ms
^C
--- www.google.com ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1001ms
rtt min/avg/max/mdev = 8.848/8.848/8.849/0.094 ms
root@eve-ng
```

#### Launch EVE-PRO installation manually

```
root@eve-ng:~# cd /etc
root@eve-ng:~# ./eve-setup
```

Step 25: Proceed to section 4 "Obtain EVE-NG Professional license"

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17

#### 3.1.2 VMware workstation OVF deployment

Download EVE-NG Professional OVF image zip file, place it in the dedicated HDD storage for EVE VM and unzip it:

https://www.eve-ng.net/index.php/download/

© EVE-NG LTD Page 23 of 263




#### 3.1.2.1 Deployment and VM machine settings

Step 1: VMware workstation or VM Player, Menu File/Open




Step 2: Browse your downloaded and unzipped EVE-PRO, EVE-PRO-VM.ovf, followed by Open



Step 3: Browse your desired EVE VM store destination followed by Import



Step 4: Open your EVE VM Settings and set the desired RAM.



Step 5: IMPORTANT Set CPU Number of Cores and number of cores per processor. Set Intel VT-x/EPT Virtualization engine to ON (checked).


NOTE: VMware Player will display only one CPU option: Number of processors.

Step 6: **Laptop PC** Select your desirable Network Adapter.

NOTE: It is recommended to choose the NAT adapter option for Laptops to avoid EVE management interface IP changes. This can happen anytime the laptop is connected to a different SSID.


© EVE-NG LTD Page 24 of 263





Step 7: **Desktop PC** Select your desirable Network Adapter.

NOTE: Desktop PC EVE management interface can be either NAT or Bridged to home LAN subnet.



Step 8: Power ON your EVE VM and follow Management IP setup instructions described in section 3.5.1 for Static IP or 3.5.2 for DHCP IP.

Step 9: Proceed to section 4 "Obtain EVE-NG Professional license"

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17

#### 3.1.2.2 OVF VM update to the latest EVE version

Step 9: Make sure if your EVE OVF VM is up to date to the newest EVE version. Follow the steps described in section 5.

© EVE-NG LTD Page 25 of 263



#### 3.1.2.3 OVF VM HDD Size expansion

▲ IMPORTANT NOTE: DO NOT expand the current EVE OVF HDD. To expand your EVE system size, please follow Troubleshooting section 16.2


#### 3.2 VMware ESXi


#### 3.2.1 VMware ESXi EVE installation using ISO image (preferred)

▲ Mandatory Prerequisites: Internet must be reachable from your Server and ESXi. EVE ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must work as well, to check it, do a named ping, for example ping www.google.com

Download EVE-NG Professional ISO distribution image: <a href="https://www.eve-ng.net/index.php/download/">https://www.eve-ng.net/index.php/download/</a>

#### 3.2.1.1 EVE-NG ESXi VM Setup and Settings






© EVE-NG LTD Page 26 of 263




Step 5: IMPORTANT Customize your EVE VM CPU Settings. Set CPU Number of Cores and number of cores per processor. Set Intel VT-x/EPT Virtualization to ON (checked).




Step 6: Assig desirable RAM for your EVE



Step 7: Set the size of HDD for your new EVE VM. It is recommended to set "Thick Provisioned eagerly provisioned". Server EVE HDD is recommended to set at least 500Gb



Step 8: Set your Management network. Adapter type VMXNET3




NOTE: Additional Network Adapters can be added for further use.

Step 9: Add new device to your EVE VM, CD/DVD

Step 10: Set DVD drive to "Datastore ISO File" and browse your uploaded EVE-PRO.iso. Make sure that Status is checked ON, "Connect at power on"

© EVE-NG LTD Page 27 of 263






#### 3.2.1.2 EVE-NG ESXi VM Installation steps

Mandatory Prerequisites: Internet must be reachable from your PC and VMware. EVE ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must work as well, to check it, do a named ping, for example ping www.google.com

#### **EVE ESXi VM Installation from ISO has 3 Phases**

#### Phase 1 (Ubuntu installation)



Step 2: Be sure if "Install EVE PRO VM" is highlighted. Confirm with Enter.




Step 3: Make sure if English is selected and confirm with Enter.

Step 4: You can select your own Location, or later, after management IP assignment, location will be set automatically. You can leave United States. Confirm with Enter

© EVE-NG LTD Page 28 of 263







Step 5: **DHCP ENABLED**, EVEs hostname by default is **eve-ng**. You can change it if you wish. Using the Tab key select continue and confirm with Enter. Continue to **Step 14** 



Step 6: **DHCP DISABLED**/Static IP setup. If you have not enabled DHCP in the network, you must assign an IP address manually. Confirm Continue with Enter.




Step 7: Confirm selection "Configure network manually" with Enter



Step 8: Enter your desirable EVE management IP, using the Tab key select "Continue" and confirm with Enter

© EVE-NG LTD Page 29 of 263





Step 9: Correct your subnet mask, using the Tab key select "Continue" and confirm with Enter




Step 10: Correct your Gateway IP, using the Tab key select "Continue" and confirm with Enter



Step 11: IMPORTANT. Name server must respond to the Internet and will be used during the next install steps. Enter your name server IP. Using the Tab key select "Continue" and confirm with Enter



Step 12: EVE hostname by default is **eve- ng**. It can be changed if you wish. Using the
Tab key select continue and confirm with
Enter



© EVE-NG LTD Page 30 of 263



Step 13: Enter your network domain name. You are free to use any, for example: eve-ng.net
Using the Tab key select continue and

Using the Tab key select continue and confirm with Enter




Step 14: If your DNS IP settings are correct, Ubuntu will detect your location from Internet. Confirm with Enter.



Step 15: Select Continue and confirm with Enter. If required, proxy settings can be configured later using EVE WEB GUI System/System Settings described in section 3.5.3



Step 16: Select **no automatic** updates and confirm with Enter. Security updates can be run later manually from EVE cli.



#### EVE VM Installation Phase 2 (EVE installation)

Step 17: Continue with Enter, the EVE VM will reboot and finish the installation phase 2

Step 18: Once EVE login screen appeared, login in CLI with root/eve and follow installation Phase 3

© EVE-NG LTD Page 31 of 263





#### EVE VM Installation Phase 3 (Management IP setup and updates)

```
Step 19: Setup EVE Management IP address. A Static IP address setup is preferred

Follow steps in section:

apt update apt upgrade

3.5.1 for static IP, 3.5.2 for DHCP IP

Follow steps in section: 5.1, 5.2
```

**NOTE:** Verify your EVE-NG server installation, type "dpkg -l eve-ng-pro" command, it must display latest EVE Pro version

```
root@eve-ng:~# dpkg -1 eve-ng-pro
Desired=Unknown/Install/Remove/Purge/Hold
     Status=Not/Inst/Conf-files/Unpacked/halF-conf/Half-inst/trig-
aWait/Trig-pend
|/ Err?=(none)/Reinst-required (Status, Err: uppercase=bad)
||/ Name
                              Version
                                                Architecture
Description
______
                         4.0.1-3
ii eve-ng-pro
                                         amd64
                                                          Α
new generation software for networking labs.
root@eve-ng:~#root@eve-sat01:~#
```

**NOTE:** If your newly installed EVE-PRO shows nothing like above, you must check your internet reachability and verify DNS configuration on your EVE-PRO server.

```
root@eve-ng:~# ping www.google.com
PING www.google.com (172.217.22.164) 56(84) bytes of data.
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=1
ttl=120 time=8.84 ms
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=2
ttl=120 time=8.84 ms
^C
--- www.google.com ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1001ms
rtt min/avg/max/mdev = 8.848/8.848/8.849/0.094 ms
```

© EVE-NG LTD Page 32 of 263



root@eve-ng

#### Launch EVE-PRO installation manually


root@eve-ng:~# cd /etc
root@eve-ng:~# ./eve-setup

Step 21: After update, Step 20 is completed, continue with type:

apt install eve-ng-dockers

This can take some time depending on your Internet connection and disk speed.

Your output after install must look like:



You must get output like in the step 21.

apt install --reinstall eve-ng-dockers

please run the command:

Step 22: (Optional) If after dockers first install

(Step 21) in the output "dc images" you still

seeing some docker name in the list as

Step 23: After Steps 20-22 are completed and you are back on the EVE CLI prompt, reboot EVE by typing

reboot

NOTE: If you are installing EVE in the locked environment and cannot install dockers online, please contact with us: <a href="mailto:info@eveng.net">info@eveng.net</a> for offline dockers installation option.

Step 24: Go to section 4 to obtain a license for EVE-NG Professional


▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17


<none>,

#### 3.2.2 VMware ESXi OVF deployment

Download EVE-NG Professional OVF image zip file, and unzip it: https://www.eve-ng.net/index.php/download/

#### 3.2.2.1 ESXi OVF VM Setup and Settings





Step 2: Set option Deploy a virtual machine from an OVF or OVA file

© EVE-NG LTD Page 33 of 263







Step 3: Type the name for your new EVE VM and browse to select all your downloaded and unzipped EVE files.

Step 4: Select VM will be de VM wi


Step 4: Select the storage where your EVE VM will be deployed.



Step 5: Select your Management network and **Thick Disk provisioning**. EVE OVF HDD is only 40Gb large. It is recommended after installation to add extra HDD. Section **16.2** 




Step 6: IMPORTANT Open VM Settings. Set the quantity of CPUs and number of cores per socket. Set Intel VT-x/EPT Hardware Virtualization engine to ON (checked).



© EVE-NG LTD Page 34 of 263



#### Step 7: Set desirable RAM for your EVE.



Step 8: Power ON your EVE VM and follow Management IP setup instructions described in section 3.5.1 for Static IP or 3.5.2 for DHCP IP.

Step 9: Proceed to section 4 "Obtain EVE-NG Professional license"

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17

#### 3.2.2.2 ESXi OVF VM update to the latest EVE version

Make sure that your EVE OVF VM is up to date with the newest EVE version. Follow the steps described in section 5 for upgrade instructions

#### 3.2.2.3 ESXi OVF VM HDD Size expansion

NOTE: IMPORTANT! DO NOT expand the current EVE OVF HDD. To expand your EVEs system disk size, please follow the troubleshooting section 16.2

#### 3.3 Bare hardware server EVE installation

Download Ubuntu 18 Server ISO distribution image:

https://releases.ubuntu.com/18.04/ubuntu-18.04.5-live-server-amd64.iso

Mandatory Prerequisites: Internet must be reachable from your Server. This ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must resolve names!

#### 3.3.1 Ubuntu Server Installation Phase 1


Step 1: Create a bootable DVD disk or USB flash drive with an Ubuntu server image. Boot your server from ISO. Make sure that English is selected, Confirm with Enter

Step 2: Select "Update to the new installer" Confirm with Enter

© EVE-NG LTD Page 35 of 263










Step 4: It is strongly recommended to use Static IP address for bare metal server. Use Tab key and select ensXXX ethernet interface to edit, confirm with Enter





Step 6: Hit Enter, to select IPv4 method. Use down arrow key to select Manual. Confirm with Enter



© EVE-NG LTD Page 36 of 263






Step 9: Select Done and confirm with Enter. If required, proxy settings can be configured later using EVE WEB GUI System/System Settings described in section 3.5.3



Step 10: If your network and DNS is configured properly, Ubuntu install will offer ubuntu mirror address from closest source. Continue with Enter.



Step 11: Leave all default settings. Make sure is selected "Use entire disk" and "Set up this disk as LVM group". Unselected "Encrypt the LVM group with LUKS". Select Done and confirm with Enter.



Step 12: Verify your HDD setting, select Done and confirm with Enter

```
Storage configuration [ Heip ]

FILE SYSTEM SUMMARY

MOUNT FOINT SIZE TYPE DEVICE TYPE

[ 184,986 new ext4 new LVM logical volume | 1 |

AVAILABLE DEVICES

DEVICE TYPE
[ Ubuntu-vg (new) | LVM volume group | 298,9966 | 1 |

[ Create volume group (LVM) | 1 |

USED DEVICES

DEVICE TYPE
[ Ubuntu-vg (new) | LVM volume group | 298,9966 | 1 |

[ Create volume group (LVM) | 1 |

USED DEVICES

DEVICE TYPE
[ Ubuntu-vg (new) | LVM volume group | 298,9966 | 1 |

[ Available Devices | LVM volume group | 298,9966 | 1 |

DEVICE | LVM volume group | 298,9966 | 1 |

[ LVM volume group | 298,9966 | 1 |

LVM volume group | 298,9966 | 1 |

[ LVM volume group | 298,9966 | 1 |

LVM volume group | 298,9966 | 1 |

[ LVM volume group | 298,9966 | 1 |

LVM volume gro
```

© EVE-NG LTD Page 37 of 263





Step 14: Using the Tab key fill your user details, select Done and confirm with Enter

Profile setup [ Help ]

Enter the username and password you will use to log in to the system. You can configure SSH access on the next screen but a password is still needed for sudo.

Your name: Setup.

Your server's name: Setup.

The name it uses when it talks to other computers.

Pick a username: Setup.

Choose a password: Sex.

Confirm your password: Sex.

```
Step 17: Wait till your server finish Ubuntu install. Using Tab key select Reboot Now and confirm with Enter

Install complete:

Install complete:
```

© EVE-NG LTD Page 38 of 263



Step 19: Use your previously created username and password to login in server. Example in this how steps was user/eve

\*\*Ubuntu 18.04.5 LTS eveng ttyl\*\*

\*\*Decumentation: https://heip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.com/obuntu.ge/decuments/ intops://beip.ubuntu.ge/decuments/ intops://beip.ubuntu.ge/decuments/ intops://beip.ubuntu.ge/decuments/ intops://beip.ubuntu.ge/decuments/ intops://buntu.ge/decuments/ intops://beip.ubuntu.ge/decuments/ intops://buntu.ge/decuments/ intops://decuments/ intops://decuments/ intops://decuments/ intops://decum

```
Step 21: Create root user password.
                                            Step 22: Allow SSH access for root user.
                                            nano /etc/ssh/sshd config
passwd root
Enter new UNIX password: eve
Retype new UNIX password: eve
                                            Navigate with arrow down key to
                                            uncomment
 oot@eve–ng:~# passwd root
                                            PermitRootLogin prohibit-password
Enter new UNIX password:
                                            Change to
Retype new UNIX password:
passwd: password updated successfully
                                            PermitRootLogin yes
root@eve-ng:~# _
                                            To save edited sshd_config use keys
                                            combo:
                                            [Ctrl]+[o] Letter o (oscar)
                                            Enter
                                            [Ctrl]+[x] Letter x (x-ray) for exit
```

```
Step 23: Restart SSH service on the server.
service sshd restart
```

Step 24. IMPORTANT: expand your server LVM partition to use all size of the HDD volume. Use Putty or other native terminal access as root to the server:

```
apt clean

lvextend -1 +100%FREE /dev/ubuntu-vg/ubuntu-lv
```

© EVE-NG LTD Page 39 of 263



resize2fs /dev/ubuntu-vg/ubuntu-lv

```
root@eve-ng:~#
root@eve-ng:~#
root@eve-ng:~#
lvextend -1 +100%FREE /dev/ubuntu-vg/ubuntu-lv
Size of logical volume ubuntu-vg/ubuntu-lv changed from 149.50 GiB (38272 extents) to <299.00 GiB (76543 extents).
Logical volume ubuntu-vg/ubuntu-lv successfully resized.
root@eve-ng:~# resize2fs /dev/ubuntu-lv ubuntu-lv
resize2fs 1.44.1 (24-Mar-2018)
Filesystem at /dev/ubuntu-vg/ubuntu-lv is mounted on /; on-line resizing required
old_desc_blocks = 19, new_desc_blocks = 38
The filesystem on /dev/ubuntu-vg/ubuntu-lv is now 78380032 (4k) blocks long.
root@eve-ng:~#
```

```
Step 25: IMPORTANT: Edit network interface name

nano /etc/netplan/00-installer-config.yaml

change interface name "ensXXX" to "eth0"

To save edited 00-installer-config.yaml use keys combo:

[Ctrl]+[o] Letter o (oscar)

Enter

[Ctrl]+[x] Letter x (x-ray) for exit

Before:

"This is the network config written by 'subiquity' ethernets:
ension:
endresses:
- 192.168.90.44/24
gateway4: 192.168.90.1
nameservers:
addresses:
- 8.8.8.8
- 8.8.4.4
search: []
version: 2

After:


"This is the network config written by 'subiquity' network:
ethernets:
ethern
```

Step 26: Update interface names with single line command:

sed -i -e 's/GRUB\_CMDLINE\_LINUX\_DEFAULT=.\*/GRUB\_CMDLINE\_LINUX\_DEFAULT="net.ifnames=0 noquiet"/'
/etc/default/grub

#### Step 27: Update GRUB

update-grub



#### 3.3.2 EVE Professional Installation Phase 2

#### Step 30: Launch EVE-PRO Internet installation

wget -O - https://www.eve-ng.net/repo-bionic/install-eve-pro.sh | bash -i

© EVE-NG LTD Page 40 of 263



**Verification:** Verify your EVE-NG server installation, type "dpkg -l eve-ng-pro" command, it must display latest EVE Pro version

Step 31: After the installation is completed, **reboot EVE** and login as root first time: root/eve. Follow the Management IP setup instructions in section 3.5.1. It is strongly recommended for bare-metal installations to use a static IP address. After the IP address setup, continue with Step 32

Step 32: After your EVE is rebooted,

Login to the EVE CLI and type:

apt update
apt upgrade

Follow steps in section: 5.1, 5.2

Step 33: After update, Step 32 is completed, continue with type:

apt install eve-ng-dockers

This can take some time depending on your Internet connection and disk speed.

Your output after install must look like:



Step 34: (Optional) If after dockers first install (Step 33) in the output "dc images" you still seeing some docker name in the list as <none>,



please run the command:

apt install --reinstall eve-ng-dockers

NOTE: If you are installing EVE in the locked environment and cannot install dockers online, please contact with us: <a href="mailto:info@eve-ng.net">info@eve-ng.net</a> for offline dockers installation option.

Step 31: Update repositories

apt update
apt upgrade

Step 32: Continue to section 4 to obtain your EVE-NG Professional license

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer section 17


© EVE-NG LTD Page 41 of 263



# 3.4 Google Cloud Platform

## 3.4.1 Google account

Step 1: Connect to Google Cloud Platform (GCP <a href="https://console.cloud.google.com/getting-started">https://console.cloud.google.com/getting-started</a>




Step 2: Sign into GCP. Create a new GCP account if you do not already have one.

## 3.4.2 Goggle Cloud project

Create new project. By default, GCP will offer you a project named "My First Project". It can be used as well.


Step 1. GCP top bar, click on "My First Project"



Step 3. Enter your project name, and confirm "CREATE"


© EVE-NG LTD Page 42 of 263






This will take some time.

Step 4. Navigate: Navigation Menu/Compute Engine/VM Instances




Step 5. Navigate: top bar and select your newly created Project



Preparation of your Project can take some time. Wait until the VM Instance window finishes deployment and then press the "Create button."


© EVE-NG LTD Page 43 of 263





# 3.4.3 Preparing Ubuntu boot disk template

Step 1: Open the google cloud shell and press: "START CLOUD SHELL"



Step 2: create a nested Ubuntu 18.04 image model. Copy and paste the below command into the shell. Use copy/paste. crtl +c/ctrl +v. It is single line command (copy all command below in cli). Confirm with "enter":

gcloud compute images create nested-ubuntu-bionic --source-image-family=ubuntu-1804-lts --source-image-project=ubuntu-os-cloud --licenses https://www.googleapis.com/compute/v1/projects/vm-options/global/licenses/enable-vmx




© EVE-NG LTD Page 44 of 263



You will get the following output when your image is ready:

## 3.4.4 Creating VM

Step 1: Navigate: Navigation Menu/Compute Engine/VM Instances and press "Create"



Step 2: Assign the name for your VM


Step 3: Set your own region and zone

Step 4: Edit your Machine Configuration. General-Purpose. Choose the series of CPU platform, Preferred are *Intel CPUs Skylake or Cascade*.

Step 5: Choose your desirable CPU and RAM settings. IMPORTANT: "Deploy a container image" must be UNCHECKED.

© EVE-NG LTD Page 45 of 263





Step 6: Select Boot disk. Press Change




Step 7. Select Custom images and the *custom boot image you created previously*. Choose HDD disk type and size. HDD size can vary depends of your needs.

© EVE-NG LTD Page 46 of 263



# Boot disk Select an image or snapshot to create a boot disk; or attach an existing disk. Can't find what you're looking for? Explore hundreds of VM solutions in Marketplace. Public images Custom images Snapshots Existing disks Show images from EVE Test Show deprecated images Image nested-ubuntu-bionic Created on 22 Jun 2020, 22:50:36 Boot disk type Size (GB) Size (GB) Size (GB)

#### Step 7: Allow https traffic and create VM




#### 3.4.5 EVE-NG-PRO installation

#### Step 1: Connect to the VM with the first option "Open in browser window"



© EVE-NG LTD Page 47 of 263





#### Step 2: Launch installation with:

#### Type the below command to become root:

sudo -i

#### Start EVE-PRO installation

wget -O - https://www.eve-ng.net/repo-bionic/install-eve-pro.sh | bash -i

#### Step 3: Update and upgrade your new EVE-PRO

apt update

apt upgrade

Confirm with Y

#### Step 4. Reboot EVE. Allow some time for reboot and then press "Reconnect"

```
we version of config file /etc/console-setup/compose.ISO-8859-1.inc ...

we version of config file /etc/console-setup/compose.ISO-8859-1.inc ...


we version of config file /etc/console-setup/compose.ISO-8859-1.inc ...

The SSH connection to VM instance 'eve-pro' was lost. Learn more about improving sSH session persistence.

we version of con sev version
```

#### Step 5: VERY IMPORTANT: Setup IP

Once the IP wizard screen appears, press ctrl +c and type the below command to become root: sudo -i



© EVE-NG LTD Page 48 of 263



Now follow the IP setup wizard, section: 3.5.2.

**IMPORTANT**: set IP as DHCP!

Step 6: Dockers installation. After EVE is rebooted, reconnect the SSH session:

Type command to become root:

sudo -i

Type command to update EVE

apt update

Type command to Install Dockers

apt install eve-ng-dockers



## 3.4.6 Access to Google Cloud EVE-PRO

Use your public IP for accessing EVE via https.






Default web login: admin/eve

# 3.4.7 Optional: GCP Firewall rules for native console use

Step 1: Navigate: Navigation menu/VPC Network/Firewall rules

© EVE-NG LTD Page 49 of 263





#### Step 2: Create new firewall rule




## Step 3: Create an ingress FW rule; allow TCP ports 0-65535



© EVE-NG LTD Page 50 of 263






Step 4: Create an egress FW rule; allow TCP ports 0-65535



© EVE-NG LTD Page 51 of 263





#### Summary FW rules.



# 3.5 EVE Management IP Address setup

#### 3.5.1 Management static IP address setup (preferred)

■ IMPORTANT NOTE: EVE Docker stations for html console access are using network 172.17.0.0/16. Please avoid use this network on the EVE management or other clouds or interfaces.

The steps below will walk you through the network setup and assign a static management IP for EVE.

Step 1: Log into the EVE CLI using the default login **root/eve** After login, type your preferred root password for EVE, default is **eve. Remember it for further use.** Confirm with enter


NOTE: Typed characters in the password


Step 2: Retype your root password again and confirm with enter.

field are not visible.


© EVE-NG LTD Page 52 of 263









Step 3: Choose your EVE VMs hostname. By default, it is **eve-ng**. You can leave it as it is. Confirm with enter




Step 4: Type your domain name for your EVE VM. By default, it is example.com. The default value can be used as well. Confirm with enter



Step 5: Using the arrow keys, select the option "static", confirm your selection with the space key, followed by enter




Step 6: Type your desirable EVE management IP. Confirm with enter.




© EVE-NG LTD Page 53 of 263



Step 7: Type the subnet mask of your EVE management network. Confirm with enter.



Step 8: Type your networks gateway IP. Confirm with enter.




Step 9: Type your networks primary DNS IP. Confirm with enter.

IMPORTANT: DNS must be reachable and resolve public addresses.



Step 10: Type your network Secondary DNS IP. Confirm with Enter. IMPORTANT: DNS must be reachable and resolve public addresses.



Step 11: Type your preferred NTP server IP. It can be left empty as well; in this case, your EVE VM will automatically assign the time from its host.



Step 12: Skip this step. By default, it is set to direct connection (no proxy).


Confirm selection with enter. EVE will reboot automatically.



**NOTE:** If required, the Proxy settings can be configured later using EVE WEB GUI System/System Settings described in section 3.5.3

Page 54 of 263 © EVE-NG LTD





▲ IMPORTANT NOTE: If you are setting up your management IP for the first time (fresh EVE installation), please return to the install section and complete installation Phase 3.


## 3.5.2 EVE Management IP address setup via DHCP

⚠ IMPORTANT NOTE: EVE Docker stations for html console access are using network 172.17.0.0/16. Please avoid use this network on the EVE management or other clouds or interfaces.


The steps below will walk you through the network setup and assign a management IP for EVE via DHCP.

Step 1: Log into the EVE CLI using the default login **root/eve** After login, type your preferred root password for EVE, default is **eve. Remember it for further use.** Confirm with enter

NOTE: Typed characters in the password field are not visible.



Step 2: Retype your root password again and confirm with enter.





Step 3: Choose your EVE VMs hostname. By default, it is **eve-ng**. You can leave it as it is. Confirm with enter

Step 4: Type your domain name for your EVE VM. By default, it is example.com. The default value can be used as well. Confirm with enter


© EVE-NG LTD Page 55 of 263








Step 5: Using the arrow keys, select the option "dhcp", confirm your selection with the space key, followed by enter




Step 6: Type your preferred NTP server IP. It can be left empty as well; in this case, your EVE VM will automatically assign the time from its host.



Step 7: **Skip this step.** By default, it is set to direct connection (no proxy).

Confirm selection with enter. EVE will reboot automatically.

NOTE: If required, the Proxy settings can be configured later using EVE WEB GUI System/System Settings described in section 3.5.3



© EVE-NG LTD Page 56 of 263



▲ IMPORTANT NOTE: If you are setting up your management IP for the first time (fresh EVE installation), please return to the install section and complete installation Phase 3.


## 3.5.3 Internet proxy setup

Step 1: If you have a proxy in use for your Internet, login into your EVE WEB GUI using your EVE IP https://aaa.aaa.aaa.aaa


Default username: admin

Password: eve

Step 2: Select Tab: System/System Settings



Step 3: Enter your Proxy IP and Port following by "Submit". For authenticated Proxy, use your username and password.



© EVE-NG LTD Page 57 of 263



## 3.5.4 EVE Management IP address reset

If for any reason you need to change these settings after the installation, you can rerun the IP setup wizard. Type the following command in the CLI and hit enter:

rm -f /opt/ovf/.configured

Then type:

su -

Once you log into the CLI again, EVE will go through the network setup again. Please follow the steps in section 3.5.1 for Static IP or 3.5.2 for DHCP IP.

# 3.6 Native telnet console management setup

If you prefer to use a natively installed telnet client to manage nodes inside EVE, follow the steps below:


#### 3.6.1 Windows Native Console

Step 1: Download the EVE Windows Client integration pack:

http://www.eve-ng.net/downloads/windowsclient-side-pack Step 2: Install it as administrator




Step 3: Leave the option for UltraVNC checked. UltraVNC is very tiny and the preferred VNC client for Windows by EVE.



NOTE: The Wireshark option for EVE Professional is left unchecked, because Wireshark is already integrated into EVE PRO.

Step 4: Continue with Next. When it asks to choose Ultra VNC Options, only leave the UltraVNC Viewer checked, the rest is not needed.



© EVE-NG LTD Page 58 of 263



Step 5: Continue with Next and finish the installation.	

By default, EVE Windows Client Integration will install Putty as your Telnet Client. The default location for the EVE Windows Client Integration software and .reg files is: "C:\Program Files\EVE-NG"

#### Set the default telnet program manually in Windows 10. Example: SecureCRT


Step 1: Go to: Windows Settings/Apps/Default Apps/Choose Default Apps by Protocol

Step 2: Set your default Telnet program:



▲ NOTE: The first time click on the type of link that is used to access a running node inside EVE via telnet, the browser will ask to choose the telnet program. If you have prepared your default telnet program with the instructions above, you have to choose your default Telnet program.

#### Example: Firefox browser:



Set your default application, check the box "Remember my choice telnet links" and click Open link

#### 3.6.2 Linux Native Console

The steps below will show how to setup the native consoles pack for Linux Mint 18 (Ubuntu):

Step 1: Go to the EVE Linux Side integration pack download page: <a href="http://www.eve-ng.net/downloads/linux-client-side">http://www.eve-ng.net/downloads/linux-client-side</a>	Step 2: Open the link to GitHub  https://github.com/SmartFinn/eve-ng- integration
Step 3: Scroll down to the installation part	

Page 59 of 263 © EVE-NG LTD



Installation

Ubuntu and derivatives

You can install eve-ng-integration from the official PPA:

sudo add-apt-repository ppa:smartfinn/eve-ng-integration
sudo apt-get install eve-ng-integration

Step 4: Login as root to your Linux system and enter the commands below:

NOTE: An internet connection is required. Enter each command line below one after the other

sudo add-apt-repository ppa:smartfinn/eve-ng-integration

sudo apt-get update

For other Linux native console setup options please refer to: <a href="https://github.com/SmartFinn/eve-ng-integration">https://github.com/SmartFinn/eve-ng-integration</a>

#### 3.6.3 MAC OSX Native Console

sudo apt-get install eve-ng-integration

Download the EVE MAC OSX Client integration pack and install it:

https://www.eve-ng.net/index.php/download/#DL-OSX

# 3.7 Login to the EVE WEB GUI

EVE PRO is using https 443. Login to the EVE management UI:

https://<your\_eve\_ip>/

Default user access:

**User: admin** 

Password: eve

▲ NOTE: You can change your EVE Admin password, please refer to section 7.3.1.2

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17

© EVE-NG LTD Page 60 of 263



# 4 EVE-NG Professional Licensing

EVE-NG Professional and Learning Centre editions require purchasing and uploading a license to activate its features. Licenses are based on an annual subscription.

EVE-NG permits up to **128 accounts** to be created but restricts the number of simultaneous sessions per role to the licensed amount. To increase the number of active sessions, please purchase additional licenses on top of the base license as shown below.

▲ Definition: Simultaneous session (1 license) means one active connection to the EVE-NG Web GUI.



<u>Example1 EVE-Professional:</u> The license information page shows 2 Admin accounts. This means 2 Admin role-based accounts can be logged into the Web GUI simultaneously. If a third Admin account logs into the Web GUI, the first active Admin session will be disconnected. Please note that the first Admin's labs will keep running. EVE-NG PRO can have up to 128 accounts, but active sessions to the Web GUI are restricted to the number of purchased licenses.




<u>Example2 EVE Learning Centre:</u> The license information page shows 2 Admin and 3 Lab-user role accounts. This means 2 Admin and 3 User accounts can be logged into the Web GUI simultaneously. If a fourth User account or third Admin account logs into the Web GUI, the first User or Admin session will be disconnected. Started labs will keep running. EVE-NG Learning Center can have up to 128 accounts, but active sessions to the Web GUI are restricted by the number of licenses purchased.

#### 4.1 EVE-NG Professional Base license

EVE-NG Professional Edition - 1 Year License <a href="https://www.eve-ng.net/index.php/buy/">https://www.eve-ng.net/index.php/buy/</a>

EVE-NG PRO features multi user support and assigns all accounts as Administrators. The license allows for 2 simultaneous users.



For EVE-PRO Administrator role permissions, please see section 4.4.

© EVE-NG LTD Page 61 of 263




# 4.2 EVE-NG Learning Centre licenses

EVE-NG Learning Centre Edition - 1 Year License https://www.eve-ng.net/index.php/buy-corporate/

EVE-NG LC features multi user support and assigns accounts as Administrators, Lab-Editors or Lab-Users.

The first minimal Base A license allows for 2 simultaneous Admin users. It is necessary to use an Administrator account to create or manage EVE LC and other user's role-based accounts.



#### **EVE-NG PRO - A Base License (Mandatory)**

This license unlocks all Pro features and two active Administrator accounts sessions. This license is mandatory for EVE LC edition.

The following licenses below can vary per your needs.

EVE-NG PRO - Administrator License

This license unlocks one additional active session for the Administrator role.

The Administrator role can manage everything in EVE-NG without restrictions.

This includes creating, deleting, and modifying all folders, labs, nodes and accounts.

The Administrator is the only role that can create or modify accounts.

EVE-NG PRO - Lab-Editor License

© EVE-NG LTD Page 62 of 263



This license unlocks one additional active session for the Lab-Editor role.

The Lab-Editor role is restricted to a personal and the Shared folder and is authorized to create, delete, or modify additional folders, labs, and nodes within them.


#### EVE-NG PRO - Lab-User License

This license unlocks one additional active session for the Lab-User role.

The Lab-User role is restricted to a personal and the Shared folder and is only authorized to start, stop, and wipe nodes. An Administrator account is required to manage folders and labs within a User's personal folder.

Example: EVE Learning Centre Licensing for 1 Teacher and a 5 Students class. Licence model below includes:

- Two administrator accounts, necessary for EVE LC labs and other user account management
- One Lab-Editor-role based account, assigned to the teacher to create/manage labs and assign them to the Shared folder for Students use. The Lab-Editor role is restricted to a personal folder and is authorized to create, delete, or modify additional folders, labs, and nodes within it.
  - Optional: If wanted / needed, the Lab-Editor account for the teacher can also be replaced by an Administrator account instead.
- Five Lab-User role-based Student accounts allowing running a class with 5 simultaneous students connected to the EVE HTML GUI.



For EVE-LC role permissions, please see section 4.4.

# 4.3 EVE-NG Corporate licenses

Essentially, this is EVE Learning Centre edition with Lab-Editor role-based accounts only. This is recommended for corporate use to allow full permissions for EVE labs but to restrict being able to manage other user accounts or labs. The Lab-Editor role is restricted to a shared and a personal folder and has permissions to create, delete, or modify additional folders, labs, and nodes within them.

EVE-NG Learning Centre Edition - 1 Year License <a href="https://www.eve-ng.net/index.php/buy-corporate/">https://www.eve-ng.net/index.php/buy-corporate/</a>

EVE-NG Corporate features multi user support and assigns accounts as Administrators or Lab-Editors.

The first (mandatory) Base A license allows for 2 simultaneous Admin users. It is necessary

© EVE-NG LTD Page 63 of 263




to have an Administrator account to create or manage EVE LC and other user's role-based accounts.

Example: EVE Corporate Licensing for 5 Lab-Editor users.

License model below includes:

- Two administrator accounts necessary for EVE Corporate labs and other user accounts management (Mandatory Base license)
- Five Lab-Editor role-based accounts. The Lab-Editor role is restricted to a shared and a personal folder and has permissions to create, delete, or modify additional folders, labs, and nodes within them.



EVE Corporate role rights, please follow section 4.4.

# 4.4 User roles comparison chart

Feature	Administrator Role	Lab-Editor/Teacher role	Lab-User/Student role
User accounts management	yes	no	no
User Accounts visibility	yes	no	no
User edit modal visibility	yes	no	no
User Folder's management	yes	no	no
Full EVE root folder tree access	yes	no	no
Licencing module access	yes	no	no
Nodes management module access	yes	yes (only own running nodes)	yes (only own running nodes)
Lab management module access	yes	yes (only own running nodes)	yes (only own running nodes)
Shared lab folder management	yes	yes	no
Shared folder access	yes	yes	yes
Rename Folders	yes	yes	no
Create labs	yes	yes	no
Delete labs	yes	yes	no
Edit Custom topology mapping	yes	yes	no
Use only Custom topology mapping	yes	yes	yes

© EVE-NG LTD Page 64 of 263



Lab objects management add text, drawing on labs	yes	yes	no
Export/import labs	yes	yes	no
Nodes list management	yes	yes	yes, read-only
Networks management	yes	yes	yes, read-only
Start labs	yes	yes	yes
Stop labs	yes	yes	yes
Wipe nodes	yes	yes	yes
Console to all nodes	yes	yes	yes
Export all configs	yes	yes	no
Edit lab	yes	yes	no
Set nodes startup-cfg to default configset	yes	yes	no
Set nodes startup-cfg to none	yes	yes	no
Topology refresh	yes	yes	yes
Topology zoom	yes	yes	yes
EVE status	yes	yes	yes
Lab details UUID	yes	yes	yes
See startup configs	yes	yes	no
Delete default startup configs	yes	yes	no
Create and manage multiconfig sets	yes	yes	no
Close labs	yes	yes	yes
Lock labs	yes	yes	no
System/Stop all nodes	yes	no	no
Information tab access	yes	yes	yes
Work with more than one lab	yes	yes	yes
Lab timer function	yes	yes	no
Lab background dark mode	yes	yes	yes
Hide node labels	yes	yes	yes

# 4.5 License purchasing and activation


- ▲ Before purchasing a license, the customer must have EVE-NG Professional installed and readily accessible.
- A Recommended browser for license operations are: Chrome or Mozilla Firefox
- You must be logged in to the EVE WEB GUI as Administrator.

Step 1: Obtain your license request from the Licensing tab of the top menu of the EVE PRO WEB GUI. License requests will work only if the host machine (and hypervisor if running a VM) has Intel VT-x/EPT enabled! (See section 3 for details)

Step 2: Copy the content of the license request and keep it ready for the order process at **Step 6**. Orders without a license request cannot be processed.

© EVE-NG LTD Page 65 of 263





Step 3: Go to the EVE PRO or Learning Centre Purchase Portal and choose your Licenses and quantity.

Licenses that are unnecessary for your EVE Learning Centre or Corporate Edition licensing needs, can simply be deleted from your order by clicking on the cross next to them to remove them. Refer to sections: **4.2** and **4.3** 


#### **EVE-PRO Purchase Portal**

#### **EVE-Learning Centre or Corporate Purchase Portal**


Step 4: Choose your preferred payment method. We currently support VISA, Mastercard, Bank/Wire transfer and PayPal.



Step 5: Complete the order form. If your license is for commercial/company use, you must select Company option.



Step 6: At the end please paste your **license request content** from Step 2 and Please read and confirm the <u>EULA agreement</u>, which contains vital information about licenses. For companies, if necessary, in the Order Notes you can add additional information/reference, e.g. for your accounting department.



Step 7: After a while (usually 10-30 mins), your license is sent to the E-Mail used in the order form.

© EVE-NG LTD Page 66 of 263




- IMPORTANT: Before loading the purchased license, make sure your EVE has Internet access. Your EVE DNS settings must be configured properly to resolve the FQDN. Internet connection is required to validate your EVE license with our EVE-NG license server.
- ▲ IMPORTANT: If your EVE internet is using Proxy, make sure you have set the proxy settings described in section 3.5.3
- Offline EVE Pro license is supported for Bare EVE installs only. (Dedicated EVE server). VM Ware and Cloud environment EVE installs require Internet connection.

Step 8: Copy Content of your received License



Step 9: On your EVE WEB GUI, click on License Upload,



Paste your licence and click on Upload



#### 4.6 License deactivation

If you decide to deactivate EVE-PRO license on the host, please follow the steps below:

▲ Go to EVE CLI and type:

cd /opt/unetlab/html/

© EVE-NG LTD Page 67 of 263



rm eve-ng.lic

cp eve-ng.nolic eve-ng.lic

# 4.7 License Rehosting.

If you decide to re-install EVE-PRO or move it to another host, please follow the steps below:

#### Pre-requisites:

- EVE must have internet access!
- Only ONE EVE host must be turned ON and connected to the internet, do NOT have more than one EVE with the same license turned on at the same time!
- Step 1. Make sure that you have only ONE EVE-PRO instance with this license running.
- Step 2. Make sure you have unrestricted Internet access with a properly configured DNS server from your EVE server.
- Step 3. Load your purchased license onto EVE server you want to rehost to.
- Step 4. Reboot your new EVE
- Step 5. Wait approximately one hour for the licence validation process to finish on the host.
  - NOTE: The re-hosted EVE server must have internet access to periodically validate the license. EVE receives a token with a licence validity time of 24 hours. During those 24 hours, the re-hosted EVE can be used offline. After 24 hours the token time expires and you have to get EVE online again (for approximately 30minutes) to receive a new token.

© EVE-NG LTD Page 68 of 263



# **EVE-NG Professional Update & Upgrade**

Prerequisites: Internet access and working DNS on your EVE-NG is required.

Verify your internet reachability with named ping. Example: ping www.google.com

ping www.google.com

```
NG www.google.com (216.58.207.228) 50 bytes from arn09s19-in-f4.1e100.net bytes from arn09s19-in-f4.1e100.net bytes from arn09s19-in-f4.1e100.net
                                                                                                                                                           ttl=58
ttl=58
                                                                                      (216
(216
                                                                                                                                                                            time=19.5 ms
                                                                                                                                 icmp_seq=2
icmp_seq=3
               from arn09s19-in-f4.1e100.net
```

If your ping is success, follow next step for update. If named ping has no success, please verify your DNS IP assigned for EVE or firewall. Some cases ping can be blocked by FW, but Internet and DNS are capable to make update/upgrade.

OPTION for bare EVE installations which has bnx2x Broadcom Ethernet drivers, please rewrite your driver to the newest linux-firmware:

```
sudo apt-get -o Dpkg::Options::="--force-overwrite" install linux-firmware
```

# 5.1 EVE-NG Professional Update

It is strongly recommended to keep your EVE-NG up to date. To update and upgrade, SSH to your EVE CLI.

To verify your current EVE-NG version, please follow "CLI diagnostic information display commands" in section 16.1.1. You can verify your current EVE version from the System/System Status tab on the top menu of the WEB GUI as well.



The newest version of EVE-NG can be verified by checking the official website: http://www.eveng.net. For update to the newest EVE-NG Professional version please follow the steps https://www.eve-ng.net/index.php/1845-2/

Page 69 of 263 © EVE-NG LTD



The year 2019 Major release, EVE Professional Edition: 2.0.6 – 17 (28 November, 2019)
To Update and Upgrade your EVE-NG Professional to the newest version, please follow the steps in the Upgrade section (reboot required)

Release 2.0.6-17 notes:

IMPORTANT NOTE: !!! Before this upgrade please stop all running labs and nodes !!!

Important security update

New HTML5 Console engine Guacamole 1.0

HTML5 console background color change option

Bugfixe(s):

Native console login fix

Type the below commands followed by Enter

```
apt update
```

In case the prompt asks to confirm with Y/N, answer Yes.

# 5.2 EVE-NG Professional Upgrade

For upgrade to the newest EVE-NG Professional version please follow the steps <a href="https://www.eve-ng.net/index.php/1845-2/">https://www.eve-ng.net/index.php/1845-2/</a>

Type commands followed by Enter

```
apt upgrade
```


In case the prompt asks to confirm with Y/N, answer Yes.

**IMPORTANT NOTE:** If you are upgrading EVE PRO from older version, the installation may ask you to confirm additional! Information:

Answer for prompt above is "N"

© EVE-NG LTD Page 70 of 263





Answer for grub-pc version is: "Keep the local version currently installed"

After the completion of the update and upgrade, reboot your EVE Server. Type the following command and hit enter.

reboot

**IMPORTANT NOTE:** Do NOT make EVE updates or upgrades from within the HTML5 Desktop console!

© EVE-NG LTD Page 71 of 263



# 6 Types of EVE management consoles

⚠ IMPORTANT NOTE: EVE Console TCP ports. EVE Pro uses a dynamic port range between 1-65000. Dynamic means that every time you start a node on the lab, EVE assigns any free port from this range for Telnet, VNC or RDP access. Static TCP port assignment for Telnet sessions is not available in EVE PRO.

EVE Pro supports three different console types.

# 6.1 Native console




EVE Native console option requires locally installed software to access your lab nodes. To use the Native console option, you must have Administrator rights on your PC and ensure the TCP port range 1-65000 is not blocked by a firewall or antivirus software.

#### 6.1.1 Native Console: telnet


**Windows OS:** You can use your preferred telnet program like Putty, SecureCRT or others. Example: Putty as native telnet client on Windows.

To setup Windows native telnet client please follow section 3.6.1



Linux OS: You can use your preferred telnet program like the Native Terminal, SecureCRT, or others

Example: Telnet client from the native terminal on Linux Mint. To setup Linux native telnet client please follow section 3.6.2



© EVE-NG LTD Page 72 of 263



**MAC OSX:** You can use your preferred telnet program like the native Terminal, SecureCRT, or others.

Example: Telnet client from the native terminal on MAC OSX. To setup MAC OSX native telnet client please follow section 3.6.3


#### 6.1.2 Native Console: Wireshark

EVE Professional has an integrated Wireshark Docker station. This allows live captures without having Wireshark installed on the client machine. The EVE Capture console uses an integrated HTML session.

Right click on the node you wish to capture, choose capture and the interface. Capture Session will open in a new browser window.

EVE-PRO supports packet captures on ethernet and serial interfaces. Select the interface frame type which will be captured:


- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.



Integrated HTML RDP for Wireshark capture

© EVE-NG LTD Page 73 of 263





Example: RA-CE live interface G0/1 capture.

To save the captured file on your local PC, please refer to section 12.1

#### 6.1.3 Native Console: VNC

**Windows OS:** Recommended and tested is UltraVNC but any other compatible one can be used.


Example: UltraVNC as Native VNC client on Windows. To setup Windows native VNC client please follow section 3.6.1



**Linux OS:** Remote Desktop Viewer for VNC Sessions. Example: Remote Desktop Viewer for VNC sessions on Linux Mint. To setup Linux native Remote Desktop Viewer please follow section 3.6.2

© EVE-NG LTD Page 74 of 263






**MAC OSX:** Preferred VNC program: Chicken VNC Example: Chicken VNC as Native VNC client on MAC OSX. To setup MAC OSX native RDP Viewer client please follow section 3.6.3


#### 6.1.4 Native Console: RDP

#### Windows OS: Windows Native RDP.

Example: Windows RDP session to Win10 host in the lab.



**Linux OS:** Remote Desktop Viewer as RDP session to lab Win10 host. Example: RDP session to Win10 host in the lab. To setup Linux native Remote Desktop Viewer please follow section 3.6.2



**MAC OSX:** Remote Desktop Viewer as RDP session to lab Win10 host. Example: RDP session to Win10 host in the lab.

To setup MAC OSX native RDP Viewer client please follow section 3.6.3

© EVE-NG LTD Page 75 of 263




## 6.2 HTML5 console



The EVE PRO HTML5 console provides a clientless solution for managing labs and node sessions. Management is achieved directly through the browser by using the Apache Guacamole HTML5 Engine. It is very convenient for Corporate users with restricted Workstation permissions (Locked Telnet, vnc, rdp).

#### 6.2.1 HTML5 Console window functions



#### 6.2.2 HTML5 Console: Telnet


HTML5 Telnet console is integrated and opens telnet sessions in the browser.

© EVE-NG LTD Page 76 of 263






**Option:** The new Chrome v70.0.3538.110 and higher allows the use of the copy/paste function inside the HTML session. Type in your Chrome browser "**chrome://settings/content/clipboard**" and press **Add** to allow the use of the clipboard extension for your EVE Server: **https://your\_ip:443** 



**Option:** The new Firefox v63.0.3 and higher allows the use of the copy/paste function inside the HTML session. Type in your Firefox browser "**about:config**" and enable clipboard values below:



#### 6.2.3 HTML5 Console: Wireshark


Right click on the node you wish to capture, choose capture and the interface. Capture Session will open in a new browser window.


© EVE-NG LTD Page 77 of 263



EVE-PRO supports packet captures on ethernet and serial interfaces. Select the interface frame type which will be captured:

- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.





To save captured file to your local PC, please refer section 12.2

## 6.2.4 HTML5 Console: VNC

HTML5 VNC console is integrated and opens VNC sessions in the browser.


© EVE-NG LTD Page 78 of 263





#### 6.2.5 HTML5 Console: RDP

HTML5 RDP console is integrated and opens RDP sessions in the browser. For Windows 7, 8, 10, Windows Server 2012, 2016 please mind the note below.




IMPORTANT NOTE: For all Windows nodes, the console type must be set to RDP-TLS in the node template. RDP-TLS node console option is actually only used with HTML5 RDP sessions.

The username and the password can be configured in the node edit settings. This will allow you resize HTML RDP console without re-login in the windows host.

© EVE-NG LTD Page 79 of 263



Example below, Edit node, Win10, Console type rdp-tls, username: user and password: Test123



## 6.3 HTML5 Desktop console




EVE PRO HTML5 Desktop provides a full-featured clientless solution for managing labs and node sessions. Management is achieved directly through the browser by using an integrated docker desktop that is accessed through the Apache Guacamole HTML5 Engine. The docker contains a full featured Linux desktop and is very convenient for corporate users with restricted workstation rights (locked telnet, vnc, rdp).

© EVE-NG LTD Page 80 of 263



## 6.3.1 Login to HTML5 Desktop console

Step 1: On your first login to the EVE HTML5-Desktop console, EVE will open a new HTML window session to an integrated Docker management station. On the Desktop you will see another EVE login icon.




Step 2: Double-click the "Link to EVE | Login" icon and log into EVE using NATIVE console.



Inside of the integrated docker station, it will open another session to EVE. All features inside of the Docker Desktop will work as you are used to with the Native console.

## 6.3.2 HTML5 Desktop Console: telnet

The integrated management docker station telnet client allows you to telnet to nodes. Telnet sessions are in a tabbed style as shown below.



© EVE-NG LTD Page 81 of 263




## 6.3.3 HTML5 Desktop Console: Wireshark


Right click on the node you wish to capture, choose capture and select the relevant interface. The capture will open in an RDP session window.

EVE-PRO supports packet captures on ethernet and serial interfaces. Select the interface frame type which will be captured:

- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.



The integrated management docker station Wireshark client allows you to capture and save captured files onto the docker station. For instructions on how to save files to your local PC, please refer to section 12.3




## 6.3.4 HTML5 Desktop Console: RDP

The integrated management docker station RDP client allows you to open Remote Desktop sessions to Windows nodes. For directions on how to transfer files to the local PC, please refer to section 13

© EVE-NG LTD Page 82 of 263





## 6.3.5 HTML5 Desktop Console: ThinClient Files exchange

The HTML5-Desktop console offers an amazing feature that allows you to exchange files between your host PC and the EVE management Linux host. Please refer to section 13 for detailed instructions.


© EVE-NG LTD Page 83 of 263



# 7 EVE WEB GUI Management

## 7.1 EVE Management Page

The Main EVE management window



The lab preview actual picture appears after 3-5 seconds.

## 7.1.1 Management buttons




Button	Description
0	Select All or Deselect All folders or labs in the EVE tree
h	Create/Add new Lab
1	Change selected item name. To use this option, please select the folder or lab that you want to rename. You must not rename the Shared folder, the Users folder or any folder inside the Users folder.
%	Move selected item(s) to a different location. To use this option, please select the folder(s) or lab(s) that you want to move.
î	Delete selected folders or labs. You must not delete the Shared folder, the Users folder or any folder inside the Users folder.
*	Import an EVE lab or lab folder from a previous export. Import file must be in .zip format

© EVE-NG LTD Page 84 of 263



<b>±</b>	Export EVE lab or folder. Select folder(s) and/or labs you wish to export and select this option. The export is saved to your local PC in .zip format and is ready to import to another EVE.
T	Toggle the sorting folders and labs between alphabetical and last edit date (ascending/descending cannot be changed currently).
8	Refresh current folder content


## 7.1.2 Management tabs



Tab	Description
<b>₩</b> Main	Returns back to the EVE Home Management screen.
<b>۶</b> Management →	Management dropdown, opening the management submenu.
<ul><li> User management</li><li> □ Node management</li><li> □ Lab management</li></ul>	Management submenu, refer to sections: 7.3, 7.3.2, 7.3.3
<b>■</b> System <b>→</b>	System dropdown.
<ul> <li>System Settings</li> <li>Cluster Management</li> <li>System status</li> <li>System logs</li> <li>Stop All Nodes</li> </ul>	System submenu, refer to section 7.4
<b>③</b> Information <b>→</b>	Information dropdown
	Information submenu, for details see section 7.5

© EVE-NG LTD Page 85 of 263





## 7.2 Folders and Lab files management

This section will explain how to manage folders and labs on the EVE management page.

## 7.2.1 Folders Management

EVE Professional has three default folders used for various operations. These must not be deleted or renamed (see below).



- Admins can create additional folders for any user.
- Editors can create or manage folders in their own profile/folder or within the Shared folder

#### 7.2.1.1 Default folder Running

EVE professional allows a single user to run multiple labs and switch between them with the Running folder.



#### Example:


- Start a lab and close it
- Open and start another lab and close it

When you open your Running folder, you will see both running labs in it. It is easy to switch between labs.

The example below is showing two running labs in the Running folder.

© EVE-NG LTD Page 86 of 263





#### 7.2.1.2 Default folder Shared

To manage the Shared folder an Admin or Editor user account is required.


The EVE Professional Shared folder is visible to all EVE users. Admin and Editor Accounts can create folders or labs and place them into the Shared folder.




**Example:** An Admin creates a lab and places it into the Shared folder.

Step 1: Create a lab, refer to section 9.1

Step 2: Select the lab you wish to move to the Shared folder and press **Move to** (or create it in the Shared folder from the start).



Step 3: Another user account can use the lab placed by the Admin in the Shared folder



NOTE: Every user has its own profile; this means that every user has an independent Running folder where this lab runs independently from other users.

© EVE-NG LTD Page 87 of 263



- NOTE: Labs can be created and modified (e.g. settings and preconfigs) by an Admin or an Editor user. The User role can use the lab only exactly the way it was configured by an Admin or Editor and is unable to change any settings.
- ▲ NOTE: Admins and Editors can create folders and labs inside the Shared directory

#### 7.2.1.3 Default folder Users


To manage the Users folder, an Admin user account is required.

The Users directory is a default EVE folder where Editors and Users have their personal folders stored.



Once an Admin has created a new Editor or User account, EVE will automatically create a folder with the user login name under the default directory Users.

**Example:** Below you can see the folders for the users with the following login names: **test2**, **test3** and **test4** 




▲ NOTE: An Admin can manage any user's folder or place labs in it.

#### 7.2.1.4 Create folder

An Admin or Editor user account is required.

Type the new folder name and click "Add Folder"

NOTE: Editors can only create folders
within their own profile folder or in the Shared folder




#### 7.2.1.5 Delete folder

An Admin or Editor user account is required.

Select the folder you wish to delete and press Delete.

- NOTE: All folder content will be deleted as well.
- NOTE: Editors can only manage their own or the Shared folder



© EVE-NG LTD Page 88 of 263



#### 7.2.1.6 Move Folder


An Admin or Editor user account is required.

Select the folder you wish to move and press the Move to button.

▲ NOTE: Editors can only manage their own or the Shared folder




Select the target destination for your folder and confirm by clicking on Move.




#### 7.2.1.7 Export Folder

Select the folder(s) you wish to export from your EVE and press Export.



Save the exported file as .zip to your local PC. The exported zip file is ready to import to another EVE instance.



If your browser is set to save downloaded files to a default directory, your exported file will be saved in the browsers default downloads directory.


#### 7.2.1.8 Import Folder

▲ IMPORTANT: Importable file MUST be in .zip format, do NOT unzip the file.


Page 89 of 263 © EVE-NG LTD



Step 1: Press the Import button.




Step 2: Choose the zipped file that contains EVE folders with labs.



Step 3: Press the Upload Button



Step 4: After you made sure your folder is imported and has all its content (labs), you can close the upload session.



## 7.2.2 Lab files Management

You can manage created labs from the main EVE file manager window

© EVE-NG LTD Page 90 of 263






#### **7.2.2.1** Create Lab

The Admin or Editor user account is required.

▲ NOTE: An Editor can create labs only within his personal folder or in the Shared folder

Click on the New Lab button and refer to section 9.1




#### **7.2.2.2** Delete Lab

The Admin or Editor user account is required to delete labs.

▲ NOTE: An Editor can delete labs only within his personal folder or in the Shared folder

Step 1: Select the lab or labs you wish to delete and then press the Delete button



#### 7.2.2.3 Clone Lab

The Admin or Editor user account is required to clone labs.

▲ NOTE: An Editor can create labs only within his personal folder or in the Shared folder

The cloning feature provides a very convenient way to duplicate original labs to share with others or base another lab on it.


Cloned labs will copy exported configs (on supported nodes) but will not copy saved states/configurations in Qemu nodes like Windows hosts, Cisco ISE, or other Qemu nodes that

© EVE-NG LTD Page 91 of 263



are not supported by the export config feature. Please refer to section 11.1 for more information on configuration export for labs.

Step 1: Select the lab you wish to clone and move the mouse pointer (blue) to that lab, an extra option will appear. Click on Clone.



Step 2: Your lab will be cloned with all your exported configurations or configuration sets with a new name.



Step 3: The lab has been cloned lab and can be renamed to your liking. Move the mouse pointer to the cloned lab and choose Rename.



Step 4: Rename it, and click OK to confirm



### 7.2.2.4 Move Lab

The Admin or Editor user account is required to move labs.

▲ NOTE: An Editor can create labs only within his personal folder or in the Shared folder


Step 1: Select the lab you wish to Move and move the mouse pointer (blue) to that lab, an extra option will appear. Choose Move to.



© EVE-NG LTD Page 92 of 263




Step 2: Choose the path to the new destination and confirm by clicking Move




#### **7.2.2.5** Export Lab

Select the Lab(s) you wish to export from your EVE Server and press Export.



Save exported file as .zip to your local PC. The exported zip file is ready to import into another EVE.




If your browser is set to save downloaded files to default directory, your exported file will be saved in the browsers default downloads directory.

## 7.2.2.6 Import Labs

▲ IMPORTANT: Importable file MUST be in .zip format, do NOT unzip the file.


Step 1: Press the Import button.



Step 2: Choose the zipped file which contains the EVE labs.

© EVE-NG LTD Page 93 of 263






Step 3: Press the Upload Button




Step 4: After you made sure your lab is imported, you can close the upload session.



## 7.3 EVE Management Dropdown Menu

#### 7.3.1 EVE User management



The User Management page, under the Management dropdown, will allow Admin accounts to manage other user accounts.

⚠ Only the Admin role is allowed to create or edit user accounts.

#### 7.3.1.1 Creating a new EVE User


Step 1: Open the User management submenu. Management>User management and click Add user

© EVE-NG LTD Page 94 of 263






Step 2: The Add New User management window will pop up. Fill in the main information about your EVE user




Step 3: If your user will be Radius authenticated please enable Radius checkbox. Passwords will be striped off, because authenticator will look Radius server for user password. How to setup radius server IP and Shared secret please follow Section:17.1

© EVE-NG LTD Page 95 of 263







Step 4: If you have bought other EVE licenses, you can choose the preferred user role. For licensing and user roles please refer to section 4



Step 5: Set the Console type for the user. If Console type is set exact: Native, HTML or HTM5 Desktop, user after login in the EVE will be forced to use selected Console Type. If Console Type is set to "any", user is able to choose Console type on Login page which Console will be used.



Step 6: **Sticky Lab.** Applies for User role only. Set the specific Lab for the user "sticky lab". After login in the EVE User will directed only to this lab. He cannot close the lab to get in main Lab management page. User can Start/Stop/Wipe lab, as well save his lab work on the lab devices. Follow Section: **7.3.1.5** 




© EVE-NG LTD Page 96 of 263



Step 8: Set the Cluster Satellite for the user. This applies for Editor and User roles. User will stick to selected Satellite. Editor or User will be forced to use only selected Satellite server.

If the value is set to "any", Editor role can select or change Satellite on the lab himself. User role will use Satellites set by admin on the lab.

The value "any" is set y default.



Step 9: Set the access date and time From - to. If the fields are left empty (untouched), your user will have no time restrictions for accessing the EVE Server. Account validity with time settings is available for Editor and User roles only.

Admin accounts have no time limit for account validity and resource, and Account Validity time or resource cannot be set.



Step 10: The POD number is a value assigned to user accounts automatically. POD numbers are like user profiles inside of EVE and are a unique value for every user Think of PODs like a virtual rack of equipment for each user. Admins can assign a preferred number between 1-128. Please keep POD numbers unique between users!

Step 11: Set user limitation to use eve resources. "-1" value is unlimited EVE resource. Only editor and User roles can be set for EVE resource limitation, Quota.

**Example:** editor user is allowed to run/create labs for x4 CPU and 8Gb RAM.

© EVE-NG LTD Page 97 of 263





#### 7.3.1.2 Edit EVE User


Step 1: Open the User management submenu. Management -> User management and choose which user you want to edit.



Step 2: The Edit user management window will pop up. Now you can edit necessary user information, roles, or access time. Confirm settings by pressing Edit at the bottom of the window.

© EVE-NG LTD Page 98 of 263





#### 7.3.1.3 User session termination

Administrator has rights to terminate active user session to the EVE server. Press Kick to disconnect user from EVE HTML session.



#### 7.3.1.4 User monitoring

There is a dropdown menu next to "Add User" called "More Info" that can provide additional information about your users. Click the checkbox next to the relevant information that you would like displayed. Additional columns will be added for each checkbox that is chosen.

© EVE-NG LTD Page 99 of 263






#### 7.3.1.5 User role sticky lab

**Sticky Lab.** Applies for User role only. Set the specific Lab for the user, "sticky lab". After login in the wEB, EVE User will directed only to this lab. He cannot close the lab to get in main Lab management page. User can Start/Stop/Wipe lab, as well save his lab work on the lab devices.

Pre-requisites for this feature: For Lab selection from the list, the Lab must be upload in the Shared folder by admin first. If Lab Menu is selected to "None", User can close the Lab and open another shared Lab for him.


The value "None" is set as default.



© EVE-NG LTD Page 100 of 263




## 7.3.2 EVE Node management



The Management dropdown has a submenu called "Node Management." The Node management menu displays all currently running nodes within EVE. Within this menu, an Admin account can manage or even console to any user's nodes.

- ▲ NOTE: Editor and User accounts are able to see and open console sessions to their own running nodes only
- NOTE: Admin accounts are able to see and open console session to all users running nodes



### 7.3.2.1 Node management actions

Button	Action
<b>-</b>	Open a console session to the running node
×	Stop the running node

#### 7.3.2.2 Node management filtering function

Each column in the Node Management Menu has a field or sort sign that will allow you to filter the list to only display information related to the entered value.

**Example**: Click on "CPU Usage" The CPU column will sort running nodes with most CPU consummation on the top.



Each column can be sorted alphanumerically by clicking on the column name.


**Example:** click on the column Username and EVE will sort all running nodes in alphabetic order by username.

© EVE-NG LTD Page 101 of 263





### 7.3.3 EVE Lab management




The Lab Management page, under the Management Dropdown, displays running or stopped labs for all users. In this menu an Admin account can manage or even open up any user's running labs. In the columns CPU and Memory usage will be displayed actual running lab CPU and RAM utilization.

- NOTE: Only labs which are using space on EVE HDD will be displayed.
- ▲ NOTE: Editor and User accounts are able to see and open their own running labs only
- ▲ NOTE: Admin accounts are able to see, open, and join any users running or stopped lab.



Several columns in the Lab Management Menu have a field that will allow you to filter the list to only display information related to the entered value.

Example: Enter username in the field to filter labs created by "admin"



**Example:** Click State to sort running labs on the top.



**Example**: Click on "Disk Usage" sorting labs with most HDD usage on the top

© EVE-NG LTD Page 102 of 263






#### 7.3.3.1 Lab management actions

Button	Action
墨	Open the running or stopped lab.
×	Stop the running lab. The running labs will be displayed on top of list.
<b>(</b>	Wipe lab. Clean up HDD space. NOTE: this action will delete saved lab configurations.

Once an admin has opened another user's running lab, that user's username will be displayed at the top of the left menu to help the admin keep track of which user's lab was opened.



## 7.4 EVE System Dropdown menu




The EVE System dropdown contains the system settings, Cluster Management, system utilization status, log files, and an option to stop all running nodes on the server.

© EVE-NG LTD Page 103 of 263



## 7.4.1 System Settings



- External Radius Server, IP port and shared secret key
- Proxy server IP and port, for authenticated proxy use username and password
- Template visibility is default settings for templates list on topology. Disable state (default) will not show on topology Nodes list with unloaded images. In the Nodes list will appear only uploaded images. The checkbox "Show unprovisioned templates" will show all available image templates.



- License check is value where you can set EVE user session login behave.
  - ✓ The Value Strict does not allow user login if all available licenses have active sessions (screenshot below, Insufficient Licenses). If user has finished work with EVE server and closed browser, EVE server will clear this user connection session automatically after 1 minute.
  - ✓ The Auto logout will terminate oldest connected user session to the EVE server.

Note: Administrator has rights terminate any user session, please refer Section: 7.3.1.3


© EVE-NG LTD Page 104 of 263







Disk critical size is value when EVE will start alert you about HDD space limit is reached. If you will set 5Gb value, your EVE will start show warning messages in notification area.




Color scheme gray-black

Example is showing limit set to 500GB. Recommended is set 3-5 GB value.


Html 5 terminal setting

 HTML5 Terminal settings Option to change console colour scheme, fonts, font size and backgrounds.




Management interface settings
 Option to enable IPv6 on the EVE
 Management interface

## 7.4.2 Cluster Management



The Cluster Management page, under the System Dropdown, will show Cluster Management options, and cluster members resources utilization. Please refer to Chapter EVE Cluster System 15


#### 7.4.3 System status




The System Status page, under the System Dropdown, will show EVE server resource utilization, the number of running nodes per template, current running versions of EVE and Qemu, and the current status of the UKSM and CPU Limit options.

© EVE-NG LTD Page 105 of 263





UKSM – "Ultra KSM (kernel same-page merging) is a Linux kernel feature that allows the KVM hypervisor to share identical memory pages among different process or virtual machines on the same server." It can be disabled globally for EVE on this page. It is recommended to keep UKSM **enabled**.



limit.

CPU Limit – CPU limit is used to limit CPU overloads during the nodes run time. It acts like a smart CPU usage option. If a running node reaches 80% CPU utilization, the CPU Limit feature throttles CPU use for this node to 50% until process usage drops under 30% for a period of 1 minute.


It is recommended to keep the Global CPU Limit option enabled.

CPU Limit can be turned for individual nodes in a lab. EVE node templates are set, by default, with the recommended CPU limit settings. An Unchecked CPU Limit option means that this node will boot without CPU

#### Reference:

https://searchservervirtualization.techtarget.com/definition/KSM-kernel-samepage-merging

#### 7.4.4 System logs




The System logs page, under the System Dropdown, will display EVE server log information


In the menu you can select a specific log file for inspection.

© EVE-NG LTD Page 106 of 263






### 7.4.5 Stop All Nodes



The Stop All Nodes option, under the System Dropdown, is an option that stops all running nodes on the EVE server. This option is accessible only by Admin users.

## 7.5 EVE Information Dropdown menu



The Eve Information Dropdown contains links to the EVE Website, EVE forum, EVE YouTube channel, and the web-based EVE Live Help chat.


To join the EVE Forum, in order to make posts or download materials, a forum user account must be created.

To join the EVE Live Chat for support, please use your Google account for access, or create a new user account for this chat. Please note the forum and live chat use separate user accounts.

## 7.6 EVE Licensing Dropdown menu

The EVE Licensing dropdown contains options for managing your EVE license.

The License Information Window will display the expiration date along with the number of licenses that have been activated



License information display:




© EVE-NG LTD Page 107 of 263



For License Request and License Upload, please refer to section 4.5 for more information.

## 7.7 Other Tab line info




Other items on the top menu are: Real-time clock, a shortcut to edit the currently logged in user, and a sign-out button.

## 7.8 Lab preview and global settings

Once you click on a lab in the folder tree, a main window on the right side will display schematic content of the lab as well as lab management options like open, edit, and delete.

The actual lab topology appears after 3-5 seconds.




#### 7.8.1 Lab preview window

The lab preview window displays the schematic position of nodes and their connectivity. The actual lab topology appears after 3-5 seconds. The Scale option allows you change the lab preview size.

© EVE-NG LTD Page 108 of 263





## 7.8.2 Lab preview buttons

In the lab preview, these buttons allow you to manage the selected lab.

Button	Description
Open	Opens the Lab to the Topology Canvas
Edit	Opens the Labs Global Settings. Refer to section 7.8.4 for more info.
Delete	Deletes the lab

# 7.8.3 Lab preview information

Description, version, UUID etc.

Lab Path: /test\_lab1.unl Description:
Version: 12 Here is short description of Lab
UIID: 95692558-5acb-4308-ab66-64f9b40bd31f
Author: John Tester

## 7.8.4 Lab Global Settings

Lab Global Settings Page is opened when you click on the preview window or

Edit button below the Lab

More actions

Re. Start all nodes

Wiley all nodes

Wiley all nodes

Console To All Nodes


© EVE-NG LTD Page 109 of 263





This page allows you to fill out important information about the lab. The red numbers in the picture correlate with the numbers listed below

- 1. Lab name.
- 2. Version: Version numbers allow a lab author to assign a value to a unique state of a lab. Increase the number to correspond to new developments in the lab. If left unfilled, EVE will assign a value of 1 automatically.
- 3. Author: You can add a lab author name in this field
- 4. Config Script Timeout: It is the value in seconds used for the "Configuration Export" and "Boot from exported configs" operations. Refer to section 11.3 for more information.
- 5. Lab Countdown Timer: It is the value in seconds to provide a time limit (countdown timer) for completing a lab. Refer to section 11.4 for more information.
- 6. Description: In the Description field you can write a short description of the lab.
- 7. Tasks: In the Tasks field you can write the task for your lab.






© EVE-NG LTD Page 110 of 263




# 8 EVE WEB Topology page

Once you open a lab, the topology page for that lab will open.



#### 8.1 Side bar functions

Move your mouse pointer over to the left on top of the minimized sidebar to expand the interactive sidebar as shown in below screenshot




## 8.1.1 Add an object

The "Add an object" menu can be accessed in two different ways, from the sidebar and by rightclicking on the Topology Page


© EVE-NG LTD Page 111 of 263





#### 8.1.1.1 Node object

The Node object opens the "Add a new node" window. Only nodes that appear blue in the dropdown menu can be added. A grey image name signifies that you have not yet properly uploaded an image to the proper folder. A blue image name means that at least one image exists in the proper folder for this template. If the "Show unprovisioned templates" is checked, EVE will display unloaded image templates. To hide it, uncheck "Show unprovisioned templates" checkbox or follow section Error! Reference source not found.




#### 8.1.1.2 Network object

The Network object opens the "Add a new network" window. This function is used to add any kind of network (Cloud, Bridge or NAT). For details on these, please refer to section 10


© EVE-NG LTD Page 112 of 263





#### 8.1.1.3 Picture object

The picture object opens the "Add Picture" window and allows you to upload custom topologies in jpg or png format. After uploading, you can edit these pictures and map selected areas to nodes from the topology to use your own designs as a lab topology from which you can directly connect to the nodes. For details, refer to section 11.2






#### 8.1.1.4 Custom shape object

The Custom shape object allows you to add shape elements onto the topology; these currently include squares, round squares and circles. For details, refer to section 11.1

© EVE-NG LTD Page 113 of 263






#### 8.1.1.5 Text object

The Text object allows you to add MS Office elements onto the topology. For details, refer to section 11.1.3




#### 8.1.1.6 Line object

The Line object allows you to add line elements onto the topology; these currently include single arrow, double arrows and simple lines. For details, refer to section 11.1



#### 8.1.2 **Nodes**



© EVE-NG LTD Page 114 of 263





In this window, you can make changes for nodes that are on the lab topology. More options can be found in the detailed node specific menu, for details refer to section 9.1.2.

NOTE: Running nodes are highlighted in Blue, their settings cannot be changed. You can only change settings of nodes that are not currently running.

You can change the following values:

- Node Name
- Boot image
- Number of CPUs for the node
- · Live CPU usage
- Enable or disable CPU Limit (Refer to section 7.4.3)
- IDLE PC for Dynamips node
- NVRAM in Kbyte
- RAM in Mbyte
- Live RAM usage
- Ethernet quantity. **NOTE:** The Node must be disconnected from any other nodes to make this change. You cannot change the interface quantity if the node is connected to any other node.
- Serial interface quantity, IOL nodes only. You cannot change Serial interface quantity
  if the node is connected to any other node.
- Type of Console
- Node Icon that appears on the Topology
- Startup configuration to boot from

Actions Buttons (Stopped node):

# ACTIONS




- Start node
- Stop node
- Wipe node
- Export the nodes config
- Networks
- Edit node
- Delete Node

Actions Buttons (Running node):

© EVE-NG LTD Page 115 of 263






- Console to the node
- Stop node
- Wipe node
- Export the nodes config
- Edit node
- Delete Node

#### 8.1.3 Networks



The Networks object in the sidebar will open the "Configured Networks" window.

The "Configured Networks" window will only show networks that were specifically added to the topology; it will not show node interconnections. The example below is showing information for networks on the Topology. For Cloud networks and how to connect EVE labs to a network external to EVE, please refer to section 10







- Edit Network
- Delete Network

## 8.1.4 Startup-configs




The Startup-configs object in the sidebar opens the "Startup-configs" window.

© EVE-NG LTD Page 116 of 263



This window will show you startup-config for each node (for PRO it shows the startup configs of the current config set) and if the node is set to boot from it (ON) or not (OFF).

The "Startup-configs" window in the EVE Professional version contains additional features, please refer to section 11.3.



### 8.1.5 Logical Maps

NOTE: The Logical Maps object will only appear in the sidebar after you have uploaded a custom topology picture to the lab EVE lab (Please refer to section 8.1.1.3). The Pictures object in the sidebar opens the "Picture Management" window.

For details on the Picture / custom topology feature, refer to section 11.2

#### 8.1.6 Configured Objects

Configured objects The "Configured Objects" window will display a list of all objects that are added onto the topology. For details on different objects, refer to section 11.1

NOTE: You will not see any objects in this window if none have been added to the lab yet.




#### 8.1.7 More actions

The More actions menu in the sidebar has a submenu with the following functions.

© EVE-NG LTD Page 117 of 263





#### 8.1.7.1 Start all nodes



The "Start all nodes" action will start all nodes on your topology, taking the (configurable) startup delay of each node into consideration.

⚠ IMPORTANT. Starting many nodes at once can seriously spike your CPU utilization. Please make sure that you are not using the "Start all nodes" option for heavy labs or that you have configured a proper delay between the nodes. For heavy nodes and large quantities, it is recommended to start them in smaller groups, wait for them to finish booting and then start another small group of nodes.


#### 8.1.7.2 Stop all nodes



Stopping all nodes will power off all nodes on your topology.

NOTE: It is recommended to save your (running) configurations on the nodes in your lab before you stop the lab if you want to continue where you left off the next time. Stopping the nodes will leave the images in a temporary folder and will take up space on your drive until they have been wiped.

#### 8.1.7.3 Wipe all nodes



The "Wipe all nodes" action will wipe the NVRAM or currently saved image of all your nodes in the current lab.

Example: You have saved the nodes configuration by saving the running configuration to the startup configuration. The Wipe command will delete the saved NVRAM startup configuration and on the next boot it will boot from factory defaults.

The same applies to images without configurations, e.g. a linux node. If you make modifications to the system and afterwards wipe this node, the next time it will boot from the original base image again as the modified image was deleted.

The "Wipe node" action is commonly used with initial startup configuration modifications. The Wipe node action does not delete configured startup configurations or sets. Please refer to section 11.3

© EVE-NG LTD Page 118 of 263



#### 8.1.7.4 Console to All Nodes

"Console to all nodes" will open a console to all of your running nodes in the current lab. This includes all different kinds of configured console types for lab nodes like VNC, Telnet and RDP.

#### 8.1.7.5 **Export all CFGs**

The "Export all configurations" action will export current configs to the EVE startup-configs.


Export configurations are supported for:

Cisco Dynamips all nodes	Juniper VRR
Cisco IOL (IOS on Linux)	Juniper VMX
Cisco ASA	Juniper vMX-NG
Cisco ASAv	Juniper vQFX
Cisco CSR1000v	Juniper vSRX
Cisco Nexus 9K	Juniper vSRX-NG
Cisco Nexus Titanium	Mikrotik
Cisco vIOS L3	PFsense FW
Cisco vIOS L2	Timos Alcatel
Cisco XRv	vEOS Arista
Cisco XRv9K	

For a full explanation of exporting configurations, please refer to section 11.3

#### 8.1.7.6 **Edit lab**





#### Set node's startup-cfg to default configset 8.1.7.8

Sets nodes to the default startup-config. NOTE: If you have nothing saved in the default config set for any node, that node will boot from factory default instead. This is commonly used with the wipe nodes function so the node will boot from the configured startup-config on next boot and not from the startupconfig in its NVRAM in case the node was started before already.

Page 119 of 263 © EVE-NG LTD



Please refer to section 11.3

#### 8.1.7.9 Set node's startup-cfg to none

Setting all lab nodes to boot from factory default. Used commonly with the wipe nodes function. The example below shows the steps to set a lab to boot from factory default.

Step 1: Wipe all nodes

Step 2: Set all nodes to startup-cfg none

Please refer to section 11.3

#### 8.1.7.10 Delete default startup-cfgs




▲ WARNING: this action will delete all configurations saved to your saved default config set. Please make sure that is what you want to do before you execute this.

#### 8.1.8 Refresh Topology

Sometimes it is necessary to refresh the topology if many objects are added on the topology.

## 8.1.9 Lab page zoom/unzoom



#### 8.1.10 Status


① Status Opens the EVE Status window.

Especially useful while working with labs to monitor your EVE's resource utilization. It shows EVEs CPU, RAM and disk utilization in real time. You can also see the number of running nodes per node type. For details on UKSM and CPU Limit, please refer to section 7.4.3

© EVE-NG LTD Page 120 of 263

[10:42:52] uldis joined [10:43:19] admin joined [10:43:24] admin: hello uldis [10:43:34] uldis: hello admin





#### 8.1.11 Lab details

Lab details display information about a lab, its UUID, description and lab tasks. To edit the lab description and lab tasks, please refer to section 7.8.4 and 8.1.7.6



#### 8.1.12 Lab Tasks

Opens a Lab Task feature. The EVE LabTasks is a feature that allows users (including admins and editors) to to create task or workbook for the Labs. Detailed how to create lab workbooks please refer Secton 11.5

#### 8.1.13 Lab Chat


Opens a Lab chat session between users on the same EVE server. To activate the chat, click "Lab Chat" on the sidebar. To close and exit from the chat, click "Lab Chat" on the sidebar again. The EVE Lab chat is a feature that allows users (including admins/teachers) to communicate with each other during lab sessions.

## 8.1.14 Lock Lab with password


"Lock Lab" disables some of the functions on the lab topology. If the lab is locked, you cannot move any node or object nor edit any node settings. Basically, the whole lab will be in read-only mode except for the lab settings itself, which you can still edit as Administrator or Editor from the main menu. The Lock Lab function is also used in conjunction with the countdown timer function, for details on this please refer to section 11.4

© EVE-NG LTD Page 121 of 263






To unlock a Lab, simply press on the red "Unlock Lab" button with an Administrator or Editor account.




Warning: Please remember your Lab lock password. In case of a lost password, you will not be able to recover it. Unlocking a lab / removal of password can be done by EVE-NG support only.


#### 8.1.15 Fullscreen



#### 8.1.16 Hide interface labels



#### 8.1.17 Dark mode or Light mode



© EVE-NG LTD Page 122 of 263



#### 8.1.18 Close lab

Closes the lab topology. The lab can be closed while the nodes in the lab are still running as well. It will appear as running lab under the Running folder. Please refer to section 7.2.1.1

#### 8.1.19 Logout



Log out from the EVE WEB GUI session.

## 8.2 EVE Lab topology menus

Right-clicking within the EVE topology can open new menus with various functions and options for managing nodes.

#### 8.2.1 Lab topology menu



Right-clicking on the (free/unused) canvas of the EVE topology opens a new menu. (Add-) Node, Network, Picture, Custom Shape and Text are the same functions referred to in section 8.1.1.

**Auto Align.** This function will help align objects on the topology. The lab creator does not need to worry about small displacements of objects. AutoAlign will align all objects to a virtual grid with a single click and can make neatly arranged labs look even neater.

#### 8.2.2 Connection menu



Right-clicking on the connection between nodes allows you to delete this connection.


#### 8.2.3 Cloud or Bridge network menu

Right-clicking on a Cloud or Bridge network allows you to edit or delete it.



© EVE-NG LTD Page 123 of 263





If you have chosen Edit, the Network edit window will open a window where you can change the placement, network type or name/prefix.

For details on how to operate EVE Cloud networks and external connections, please refer to section 10

### 8.2.4 Stopped node menu

Right-clicking on a stopped node also opens a menu:




Start node: This will start the selected node in this lab

**Wipe node:** Wiping a node will erase the NVRAM (running config) or the temporary image snapshot depending on the type of node. This option is used to clean up a node in order to boot it from factory defaults or a custom set of configurations.

**Edit node:** Opens the Edit node window (picture on the right). For details please refer to section 9.1.2

**Delete node**. Deletes the node from the lab. It is recommended to disconnect (delete connections to it) the node before you delete it.




© EVE-NG LTD Page 124 of 263



#### 8.2.5 Running node menu



Right-clicking on a running node also opens a menu:



**Stop.** Blue arrow: clicking on Stop will stop the node depending on the method the node supports (power off / shutdown are auto-selected based on the template)

**Stop menu.** Red arrows: There are more options to stop a node, clicking on the chevron on the left side of "Stop" opens a submenu.

- **Shutdown**: Perform an orderly shutdown of the node if that node supports it (shutdown signal is sent down to the node)
- Power off: Kills the running nodes process within EVE (hard poweroff).
- Hibernate. Save Node state (Disk and Memory are saved in an internal snapshot).
   Used for fast boot of a node. The hibernation process can take some time. Once the hibernation process is completed, the node will turn grey (shutdown state).

**Wipe node**: Wiping a node will erase the NVRAM (running config) or the temporary image snapshot depending on the type of node. This option is used to clean up a node in order to boot it from factory defaults or a custom set of configurations.


**Export CFG:** This function is used to export the saved running configuration to the EVE startup configuration sets. Reference section 11.3



**Capture**. Integrated live Wireshark capture. Select the interface which you wish to capture. Reference section 12

#### 8.2.6 Selected nodes menu and features


It is possible to select many objects or nodes at once in EVE. Using your mouse, you can select an area which will cover your nodes and/or you can click on nodes while holding the CTRL key on your keyboard.



© EVE-NG LTD Page 125 of 263



A right-click on any of the selected nodes opens a group menu:



Start Selected: This will start the selected nodes in this lab.

**Stop Selected:** This will stop the selected nodes in this lab

**Wipe Selected**: The Wipe Selected nodes action will wipe the NVRAM or currently saved image of the selected nodes in the current lab.

Example: You have saved the nodes configuration by saving the running configuration to the startup configuration. The Wipe command will delete the saved NVRAM startup configuration and on the next boot it will boot from factory defaults.

The same applies to images without configurations, e.g. a linux node. If you make modifications to the system and afterwards wipe this node, the next time it will boot from the original base image again as the modified image was deleted.

The Wipe node action is commonly used with initial startup configuration modifications. The Wipe node action does not delete configured startup configurations or sets. Please refer to section 11.3

**Console To Selected Nodes:** Console To Selected Nodes will open a console to all selected running nodes in the current lab. This includes all different kinds of configured console types for lab nodes like VNC, Telnet and RDP

**Export all CFGs:** The Export all configurations action will export current configs of selected nodes to the EVE startup-configs.

For a full explanation of exporting configurations, please refer to section 11.3

**Set nodes startup-cfg to default configset:** Sets nodes to Default startup config, used commonly with the wipe nodes function. NOTE: If you have nothing saved in the default config set for any node, that node will boot from factory default instead. This is commonly used with the wipe nodes function so the node will boot from the configured startup-config on next boot and not from the startup-config in its NVRAM in case the node was started before already.

Please refer to section 11.3

**Set nodes startup-cfg to none.** Setting selected lab nodes to boot from factory default. Used commonly with the wipe nodes function. The example below shows the steps to set selected nodes to boot from factory default.

© EVE-NG LTD Page 126 of 263



Step 1: Wipe selected nodes

Step 2: Set nodes startup-cfg to none

Please refer to section 11.3

Horizontal Align. Aligns the selected nodes in one horizontal line.

Step 1: Select the nodes you wish to align.

Step 2: Right click on one of the selected nodes and choose Horizontal align, this will align all nodes to the selected node.

#### Picture before:



#### Picture after:




**Vertical Align:** Aligns the nodes in one vertical line.

Step 1: Select the nodes you wish to align.

Step 2: Right click on one of the selected nodes and choose Vertical align, this will align all nodes to the selected node.

## Picture before Picture after



Circular Align: Aligns the nodes in a circle.

© EVE-NG LTD Page 127 of 263




Step 1: Select the nodes you wish to align.

Step 2: Right click on one of the selected nodes and choose Circular Align, this will align all nodes in a circle, the midpoint of the circle will be at the coordinates the selected node was at before.

#### **Picture Before**

#### **Picture After**




#### Delete nodes startup-config.

▲ WARNING, this action will delete the configurations of the selected nodes that are saved to your Default config set. Please make sure that is what you want to do before you execute this.

**Delete selected:** This will delete the selected nodes from your current lab.

Selected nodes can be moved as a group across the topology.

Example: You can select nodes and objects to better position them on the Topology.



© EVE-NG LTD Page 128 of 263



## 8.3 EVE Lab node states and symbols

### 8.3.1 Stopped (non-running) nodes



Grey colour and a square symbol below a node means that the node is stopped and not running. Once you will start it, the node will change to one of the running states below.



A grey node with an exclamation mark inside a triangle below the node means that there was a problem during the boot process, this could be a corrupted boot image, insufficient resources or problems with the initial configuration. A node in this state cannot be started again.

**Workaround**: Right-click on the node and wipe it, the symbol will then change to a grey colour with a square symbol below it. Then edit the node and make sure you have configured sufficient resources and the correct settings for this node, if it has startup-configs you can check them as well. Afterwards start the node again.

### 8.3.2 Running nodes



The blue color and black Play triangle symbol means that the node is started and running, the node is in a working/functional state.




A running node with a clock symbol below the node means that the node is waiting to finish loading from the set exported/startup configuration. Once the configuration has been successfully applied, the node symbol will change to a Play triangle symbol. If the node has finished booting but the clock symbol does not change to

the Play triangle symbol, the problem could be in the uploaded startup configuration. For how to use exported configurations and boot nodes from them, please refer to section 11.1



A running node with a turning red gear symbol means that the node is either in the process of hibernating the node or it has sent the shutdown signal to the node and is waiting for it to turn off. Once this process has successfully finished, the symbol

will turn into a grey node with a black square symbol below it (stopped state).



Example nodes where Stop/Shutdown is supported: Microsoft Windows and most Linux nodes as well as a lot of appliances based on linux.

#### 8.3.3 Node connector symbol



Connector symbol: If you move your mouse pointer on top of a running or stopped node, an orange connector symbol appears. It is used to connect nodes on the topology in a drag and drop style. Drag the symbol from one node and release the mouse pointer on the second node. A new window will appear where you can select the interfaces the link should connect to.

© EVE-NG LTD Page 129 of 263




## 8.4 Other

#### 8.4.1 Notifications area



The Notification area in the top right is displaying informational or error messages.

Unwrapped notifications:



The Notification messages bar appears automatically for any EVE-PRO activity made on Topology.

Success 4	Success message counter. For review, click on green ball to unwrap notifications. To wrap notifications, click to the ball again or click at any point of topology			
Error 1	Error message counter. For review, click on red ball to unwrap notifications. To wrap notifications, click to the ball again or click at any point of topology			
•	Unwrap or wrap notifications bar.			
×	Close notifications bar. Note: Notifications bar appears automatically on any EVE topology activity.			

© EVE-NG LTD Page 130 of 263




# 9 Working with EVE labs

▲ IMPORTANT NOTE: You must prepare and upload at least a couple of images to start building your labs. Refer to section 17

## 9.1 Creating a lab

Step 1: Click Add new lab. For more information on creating new labs, please refer to section 7.2.2.1



#### Step 2:


Fill out the lab information. Name and Version are required fields. Next hit Save. Refer to section 7.8.4 for more information about the different fields in the Edit lab window.



#### 9.1.1 Adding nodes to the lab

The new Topology page will open. There are two different ways to add nodes to the topology canvas:

Step 1: Object/Add Node




© EVE-NG LTD Page 131 of 263



Step 2: The Add new node window will appear. You can scroll down to choose which node you wish to add to the lab topology, or you can type the node name to filter through the node list.

NOTE: It will only be possible to select and add nodes that have images preloaded in EVE. These nodes will be displayed in a blue font. To prepare images for EVE, refer to section 0



Step 3: Edit "Add a new node" settings. Please refer to the picture and table below.

© EVE-NG LTD Page 132 of 263



Number of nodes to add 2. Image 3.  1 csr1000v-universalk9.03.17.04.S.156-1.S4*  Name/prefix 4.  CSR  Icon 5.  CPU Limit 7.  CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0) tpl(x86_64) tpl(e1000) *  QEMU custom options 14.  -machine type=pc-1.0,accel=kvm-serial mon:stdio-nographic-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefconfig-nodefco	Template 1.							
1								*
Name/prefix 4.  CSR  Icon 5.  CSR  UUID 6.  CPU Limit 7.  CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)  tpl(x86_64)  tpl(e1000)    QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notes 14.  Startup configuration 15.  None	Number of nodes to	add 2.	lmage	3.				
CSR	1		CSF10	000v-univ	ersalk	<9.03.17.04.S.	156-1.S4	4 🕶
Con   5   CSRv1000.png	Name/prefix 4.							
CPU Limit 7.  CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0) tpl(x86_64) tpl(e1000) v  QEMU custom options 14.  -machine type=pc-1.0,accel=kvm-serial mon:stdio-nographic-nodefconfig-nesseratory  Startup configuration 15.  None v  Delay (s) 16.  0  Console 17.  telnet v	CSR							
CPU Limit 7.  CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0) tpl(x86_64) tpl(e1000)   QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestatup configuration 15.  None Delay (s) 16.  0  Console 17.  telnet	Icon 5.							
CPU Limit 7.  CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0) tpl(x86_64) tpl(e1000)  QEMU custom options 14.  -machine type=pc-1.0,accel=kvm-serial mon:stdio-nographic-nodefconfig-nesserate profiguration 15.  None Poelay (s) 16.  Console 17.  telnet	CSRv1000.png							*
CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)  tpl(x86_64)  tpl(e1000)    QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestate type type to the serial mon stdio -nographic -nodefconfig -notestate type type type type type type type ty	uuid <b>6</b> .							
CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)  tpl(x86_64)  tpl(e1000)    QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestate type type to the serial mon stdio -nographic -nodefconfig -notestate type type type type type type type ty								
CPU 8. RAM (MB) 9. Ethernets 10.  1 3072 4  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)  tpl(x86_64)  tpl(e1000)    QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestate type type to the serial mon stdio -nographic -nodefconfig -notestate type type type type type type type ty	CDILLimit 7							
1  QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)  tpl(x86_64)  tpl(e1000)    QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestartup configuration 15.  None    Delay (s) 16.  0  Console 17.  telnet     Very Company of the configuration 4.	CPO LIMIT							
QEMU Version 11. QEMU Arch 12. QEMU Nic 13.  tpl(2.12.0)   tpl(x86_64)   tpl(e1000)   QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notestatup configuration 15.  None   Delay (s) 16.  Console 17.  telnet   Telnet	сри <mark>8.</mark>	RAM	(MB) 9			Ethernets	10.	
tpl(2.12.0)   tpl(x86_64)   tpl(e1000)    QEMU custom options    14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -notes    Startup configuration    None    Delay (s)    Console    To telnet    tpl(e1000)   tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(e1000)    tpl(	1	307	'2			4		
QEMU custom options 14.  -machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -nodefconfi	QEMU Version 11.	QEM	IU Arch	12.		QEMU Nic	13.	
-machine type=pc-1.0,accel=kvm -serial mon:stdio -nographic -nodefconfig -nodefconf	tpl(2.12.0) •	tpl	(×86_64)	*		tpl(e1000)		*
Startup configuration 15.  None  Delay (s) 16.  Console 17.  telnet	QEMU custom option	s 14.						
None  Delay (s) 16.  Console 17.  telnet	-machine type=pc-1.0	,accel=kvn	n -serial r	non:stdio	-nog	raphic -node	fconfig -	-D¢
None  Delay (s) 16.  Console 17.  telnet		4.5						
Delay (s) 16.  Console 17.  telnet		1 15.						_
Console 17.								•
Console 17.								
telnet	0							
Left Top	halmak							*
	temet							

## 9.1.1.1 Node values Table



© EVE-NG LTD Page 133 of 263



1.	ADD A NEW NODE  Template  Circa CER 1000V    Value Val			
2.	Number of nodes to add  Chose the number of nodes of this type you want to add to the topology			
3.	Choose your preferred version from preloaded images list (if you have more than one image loaded for a single template).			
4.	Type your preferred node name. If you are adding more than one, EVE will automatically append numbers to the nodes name.  Example. We are adding 5 CSR nodes with the name R. On the topology they will appear as R1, R2, R3, R4, R5. Later using the the Nodes window, you can edit the node names per your needs. Refer to section 8.1.2 or edit the node individually, refer to section 9.1.2.			
5.	Node icons can be changed from the default per your preference, simply choose the preferred icon from the dropdown list.  Node icons can be changed later per your needs. Refer to section 8.1.2			
6.	The UUID number is assigned automatically after a node is created. You may also set it manually in case you are using a license that is tied to a particular UUID.			
7.	CPU limit per node. This option is already set (checked/unchecked) per EVE recommendations. Refer to section 7.4.3			
8.	Each node template has a pre-set CPU value that aligns with vendor requirements. This value can be changed per your needs.			

© EVE-NG LTD Page 134 of 263



9.	Each node template has a pre-set RAM value that aligns with vendor requirements. This value is displayed in MB and may be changed per your needs.					
10.	The number of ethernets interfaces.  NOTE for IOL nodes:  Ethernet interfaces for IOL nodes are placed into groups of 4. A value of 1 for Ethernet means your node will have 4 interfaces.  The serial interface option is available for IOL nodes only and follows the same grouping structure as ethernet interfaces. A value of 1 for Serial means your node will have 4 serial interfaces.  Ethernet portgroups (4 int each)  Serial portgroups (4 int each)  1					
11.	Custom MAC address for Qemu nodes only. You can define your own MAC address for first interface:  First Eth MAC Address  aa:bb:cc:00:de:ad					
12.	QEMU Version EVE will pre-set the best recommended QEMU version for each node template. This value can be changed per your needs.					
13.	Qemu architecture is pre-set per image vendor recommendations. This value can be changed per your needs					
14.	Type of Qemu NIC is pre-set per image vendor recommendations. This value can be changed per your needs.    Virtio-net-pcl   e1000   e1000-82545em   vmx-net3   tpl(vmxnet3)   tpl(vmxnet3)					
15.	QEMU custom options  -machine type=pc-1.0,accel=kvm-cpu Nehalem-serial mon:stdio-nographic-r  recommendations. This value can be changed per your needs					

© EVE-NG LTD Page 135 of 263



16.	None boot from saved configurations. Refer to section	Startup configuration: Value can be changed to set your node to ion 11.3 for more details.				
17.	The Delay value is set in seconds and can be used to delay a node from booting after it is started. Example: if the value is set to 30, the node will wait 30 seconds before processing its boot sequense. This feature is useful in conjunction with the "Start all nodes" function if your lab requires certain nodes to start up before others or to avoid a mass-start of very heavy nodes.					
18.	Console  telnet  The setting can be changes per your needs.  NOTE: The Docker template contain therefore, please refer to section 14.1 types for each docker image. Window VNC but RDP needs to be enabled in	.3 for recommended console vs nodes can use either RDP or				
19.	Pirst Eth MAC Address  OPTIONAL: T  Cisco FirePow and Citrix hav  manually set the MAC address for the first ethernet interface. T  the use of licenses that are tied to a particular MAC address.  MAC Address format must be like: 00:50:0a:00:0b:00					

#### 9.1.2 Edit node

EVE provides two ways to edit nodes after being added to the topology canvas.

▲ NOTE: A node must be wiped each time an image or startup configuration has been changed.

## 9.1.2.1 Edit nodes globally

From the Topology page. Click "Nodes" from the left sidebar to bring up the nodes list. Refer to section 8.1.2 for more details.

© EVE-NG LTD Page 136 of 263




#### 9.1.2.2 Edit node individually.



Right click on the node and click Edit

The "Edit node" window will appear. It is very similar to the window that is displayed when you add a new node. To change values for the node, refer to the nodes value table in section 9.1.1.1.



© EVE-NG LTD Page 137 of 263




#### 9.1.3 Wipe Node




The "Wipe node" function will clear the NVRAM of the node. Each time a node setting is changed (CPU, RAM, boot image or startup configuration) a wipe must be issued on that node. For more information refer to section 11.3

#### 9.1.4 Interconnecting nodes

To connect nodes on the lab, use the drag and drop style method



The connection window will appear. Choose the interface you want to use to interconnect the nodes. Click Save when finished.




## 9.1.5 Edit connection link style

Right click on the connection link and choose Edit Style


© EVE-NG LTD Page 138 of 263







#### Straight link style



**Style**: Allows you to choose solid or dashed style for link. This can be edited later in the "Shape Edit" menu.

**Link colour**: Allows you to choose a colour for the link. This can be edited later in the "Shape Edit" menu.

Pos "interface" label: Allows move and position interface label

**Link Style**: Allows you to choose a style Straight, Bezier, Flowchart or StateMachine for the link. This can be edited later in the "Shape Edit" menu.

**Link label**: Allows you to add a label on the link. This can be edited later in the "Shape Edit" menu.

Pos Label: Allows move and position Link label, position it on the link

Curviness: Link curviness feature for Bezier style link

Midpoint: Link mid point change, Flowchart style only

Round: Link round angles, Flowchart style only

Stub: Stub link connection beside node, Straight style only

For edit Link style use mouse right click on link to call out link style editor.

#### 9.1.6 Edit connection link quality

Right click on the connection link and choose Edit Quality. This function will allow apply on live connection Delay in ms, Jitter in ms, Packet loss in % and rate in kbs.

© EVE-NG LTD Page 139 of 263





It is recommended to apply value divided by 2 on both link interfaces to achieve precise connection quality. In the example below is applied 25% and 25% packet loss, which gives result of 50% packet loss in connection between nodes.




#### 9.1.7 Suspend or resume link connection

The EVE-Pro has integrated feature to detect connection state on the interface.

Right click on the connection link and choose Suspend Link. This function will suspend connection between the two nodes. Literally, it will act like disconnected cable from the node, and interface will detect it as no connection. Suspended link will be marked with red dots.

To resume link connection, right click on the link connection and choose Resume Link





Supported nodes with suspend/resume feature:



© EVE-NG LTD Page 140 of 263



**IOL VIOS** XRv9K **CSR CSR SD-WAN ASAv** 

Firepower FTD

Juniper vSRX 12.1X47 Juniper vSRX NG

Juniper vMX VCP/VFP

Juniper VRR

Nokia Timos SR 19.5.1

Windows All Linux All Apple OSX Mikrotik Palo Alto

F5

**Fortigate** Checkpoint Cumulus Cyberoam FW

Sophos FW SonicWall FW

Viptela Velocloud

Versa Networks sd-wan

pfSense

Brocade vADX Barracuda NGFW

**HP VSR1000** 

Arista NXOS 9k ASA ported

XRv

Old Juniper vMX Juniper vQFX **Dynamips** 

**NOTE**: Avoid use Link suspend feature if you have configured:

IOL L3 router image with:


If the IOL L3 node interface is configured as DHCP client (ip dhcp), IOL node is attempting to bring up interface in up/up state. If you have enabled Link suspend feature on such configured interface, the node will flap link connection up/down/up.

Same behave is observed if your Serial interface is configured with PPP encapsulation.

#### Other observations:

vIOS L2 image has minor internal issue. LACP protocol does not detect interface state as down/down

#### 9.1.8 Delete connection between nodes



To delete a connection, right click on it and hit "Delete."

Page 141 of 263 © EVE-NG LTD



#### 9.1.9 Delete Node



To delete a node, right click it and hit "Delete." This is a non-reversable function

NOTE: It is strongly recommended to delete connections from a node before deleting the node itself.

## 9.2 Running labs

#### 9.2.1 Starting lab


Nodes inside a lab may be started individually, in groups, or all at once.

The Start all nodes option will start all nodes on your topology.


IMPORTANT. Starting all the nodes at once can result in major spikes in CPU utilization. Please make sure you are not using the "Start all nodes" option for heavy labs. Instead, it is recommended to start nodes in small groups.

Starting a node or group of nodes:

Right click on single node or node group and hit "Start."



Running nodes will turn blue. Refer to section 8.3 for node states



Page 142 of 263 © EVE-NG LTD



## 9.2.2 Interconnecting running nodes (hotlinks)


Eve Professional offers the hotlinks feature which allows you to interconnect node in the running state.



Connector symbol. Moving the mouse over a node will make an orange male plug appear. The male plug is used to connect nodes on the

topology, drag and drop style. Release the mouse pointer on the second node





## 9.2.3 Link quality delay, packet loss, jitter and rate feature

Please refer to Section 9.1.6

## 9.3 Saving labs

To save a running lab, refer to the vendor recommended save commands for each node.

Example:

Cisco: "copy run start" Juniper "commit"

Your current work will be saved in the nodes' NVRAM and the lab can be stopped safely. Starting the lab again will allow you to pick up from where you left off.

▲ WARNING: Using the wipe action on a node will clear its NVRAM. This is similar to doing a factory reset on a device.

The configurations of nodes can be exported and used as initial or startup configurations for your labs. To export configurations and configuration sets for labs refer to section 11.1

## 9.4 Stopping labs

The Stop all nodes option will stop all nodes on your topology.

NOTE: It is recommended to save your running configurations before you stop your nodes.

Stopping a node or group of nodes:

Right click on single node or node group and hit "Stop."


For individual node Stop options refer to section 8.2.5

© EVE-NG LTD Page 143 of 263



## 9.5 Start saved lab

Select the lab you want to start and click "Open". To start Lab refer section 9.2.1



## 9.6 Working with multiple running labs

Refer to section 7.2.1.1

## 9.7 Importing labs

Refer to section 7.2.2.6

# 9.8 Exporting labs

Refer to section 7.2.2.5

## 9.9 Deleting labs

Refer to section 7.2.2.2

# 9.10 Moving labs

Refer to section 7.2.2.4

© EVE-NG LTD Page 144 of 263




# 10 EVE Clouds and Networks

# 10.1 Bridge Network


The EVE Bridge interface acts like an unmanaged Switch. It supports passing along tagged dot1q packets.

Example: We have to connect many nodes in a flat (dot1q) network


Step 1: Add a Bridge Network onto the topology. There are two ways to do this: Right-clicking on the topology area and selecting "Add Network" or in the sidebar click "Add an Object" and then select "Network." Please refer to sections 8.2.3 and 8.1.1.2



Step 2: Name/prefix can be changed in order to rename your Bridge network. Make sure your network type is set to bridge.



Step 3: Connect your nodes using the drag and drop connector. Refer to sections 9.1.4 and 8.2.3




© EVE-NG LTD Page 145 of 263




#### 10.2 **Internal Network**

Internal cloud network is used as an extended connector between nodes inside of one lab. It is isolated cloud which not visible for other labs or users.

Step 1: Add two internal cloud networks onto the topology.



Step 2: Connect your lab nodes to internal cloud. Your configured nodes will work like being connected to the same switch (or the same bridge in EVE). CDP works. It is convenient if it is necessary to have connections across the lab and you don't want to have connections going from one end of the lab to the other.




#### 10.3 **Private Network**

Private cloud network is used as an extended connector between labs in the one user POD. Private cloud is isolated and not visible for other users.

**Example**: one user is running multi labs (Lab1 and Lab2), and want interconnect it.

Step 1: Add private cloud network onto the topology Lab1.

Step 2: Add private cloud network onto the topology Lab2.




Step 3: Connect your lab node to Private cloud. Your connected nodes in Lab1 and Lab2 will work like being connected to the same network. CDP works. It is convenient if it is necessary to have connections across the multi labs.

▲ NOTE: Using Private cloud, avoid to connect nodes with same ID to it. It will raise MAC address collision in your connection. Pic below shows correctly interconnected Node ID1 in Lab1 and Node ID5 in Lab2.

Page 146 of 263 © EVE-NG LTD





#### 10.4 NAT Network

EVE-NG PRO has an embedded NAT interface with the subnet 172.29.129.0/24. This feature is similar to the VMWare NAT interface, but EVE is translating the 172.29.129.0/24 (this subnet is hardcoded in EVE and is not configurable) subnet to EVE's management interface pnet0.


To add a NAT Cloud onto the EVE topology:



Step 1: Add A New Network onto the topology. There are two ways to do this: Right-clicking on topology area and selecting "Network" or in the sidebar, "Add an Object" and then select "Network."

Step 2: Name/prefix can be changed in order to rename your NAT network. Make sure your network type is set to NAT.

Step 3: Connect your nodes using the drag and drop connector. Refer to sections 9.1.4 and 8.2.3



If your EVE management is connected to the Internet, adding a NAT cloud onto the EVE lab enables you to have internet access from within your EVE lab using NAT.

EVE NAT Gateway IP is: 172.29.129.254/24

DHCP is enabled on the EVE NAT Cloud.

© EVE-NG LTD Page 147 of 263



# 10.5 Management Cloud0 interface


EVE management interface is also known as the Cloud0 network for labs. The Cloud0 interface is bridged with your EVEs first NIC. "Cloud" is used as an alias to pnet. Pnet is the bridge interface name inside of EVE.

```
# The primary network interface
iface eth0 inet manual
auto pnet0
iface pnet0 inet dhcp
bridge_ports eth0
bridge_stp off
```


Cloud0 is commonly used inside EVE labs to get management access to nodes running inside EVE from a host machine external to EVE.

■ IMPORTANT NOTE: For EVE VMs running on ESXi, make sure your management interface bridged with the vSwitch (Port group) has the security settings for Promiscuous Mode set to Accept. Any port group or vSwitch used to connect an external network to an EVE Cloud network needs to have the Promiscuous mode set to "Accept"!

#### vSwitch Settings



#### **Portgroup Settings**



EVE Cloud0 bridging table.

© EVE-NG LTD Page 148 of 263



Lab name	EVE interface name (inside)	Туре	Notes
Cloud0	pnet0	Bridged	Cloud0/pnet0 is bridged with your primary EVE ethernet port. It is assigned a management IP address used for WEB GUI access. The EVE management subnet can be used as a management network in labs.

Question: How can I obtain my Cloud0 subnet and gateway IP. Many EVE VMs only have a DHCP address assigned on the pnet0 interface.

**Answer:** SSH to EVE and type the following from the CLI:

#### route

root@eve-ng:~#	route ackets 146	errors:0 dropped:0	overrui	ns:0 car	rier:O	шут	
Kernel IP rout	ting table						
Destination	Gateway	Genmask	Flags	Metric	Ref	Use	Iface
default	192.168.90.1	0.0.0.0	UG _	0	0	0	pnet0
172.17.0.0	×	255.255.0.0	U	0	0	0	docker0
172.29.129.0	iteway IP type:	255.255.255.0	U	0	0	0	nat0
192.168.90.0		255.255.255.0	U	0	0	0	pnet0
coot@eve-ng:"#	<del>,</del>						

**Example:** We want to use Cloud0 as a management network for an ASAv node in an EVE lab. From the above-obtained information, we know that our Cloud management subnet is 192.168.90.0 with a mask of 255.255.255.0 and the Gateway IP is 192.168.90.1.



Step 1: Add A New Network onto the topology. There are two ways to do this: Right-clicking on topology area and selecting "Network" or in the sidebar, "Add an Object" and then select "Network."


Step 2: Name/prefix can be changed in order to rename your Cloud0 network. Make sure your network type is set to Management(Cloud0).

Step 3: Connect your ASAv using the drag and drop connector to the Cloud0 network. Refer to sections 9.1.4 and 8.2.3


Step 4: Start the node and configure the interface connected to Cloud0 with an IP address from the management subnet (192.168.90.0/24 in this example). Make sure you do not assign duplicate IPs.

© EVE-NG LTD Page 149 of 263






The native management host (home PC) can be used to manage nodes in the EVE lab over https. Example below showing http connection to Fortigate FW node in the EVE lab from native PC using Chrome browser.



**NOTE:** Cloud interfaces can be used to connect multiple nodes to a single cloud instance on the topology.



# 10.6 Other cloud interfaces

Other cloud interfaces can be used to extend a lab connection inside of EVE or bridged with other EVE interfaces to connect external networks or devices.

© EVE-NG LTD Page 150 of 263



### EVE Cloud bridging table.

Lab cloud name	EVE interface name (inside)	Туре	ESXi VM corresponding interface	VMware Workstation corresponding interface	Bare HW Server	Notes
Cloud0	Pnet0	bridged	Network adapter 1	Network Adapter	First ethernet Eth0	Cloud0/pnet0 is bridged with your primary EVE ethernet port. It is assigned a management IP address used for WEB GUI access. The EVE management subnet can be used as management network in the labs.
Cloud1	Pnet1	bridged	Network adapter 2	Network Adapter 2	Second ethernet Eth1	Cloud1 can be bridged with your EVE second ethernet port to achieve connection to another network or device. The IP address is not required to be configured on it. It will act like a pure bridge your external connection with EVE lab node.
Cloud2	Pnet2	bridged	Network adapter 3	Network Adapter 3	Third ethernet Eth2	Same as Cloud1
Cloud3	Pnet3	bridged	Network adapter 4	Network Adapter 4	Fourth ethernet	Same as Cloud1
Cloud4-9	Pnet4-9	bridged	Network adapter 5-10	Network Adapter 5-10		Same as Cloud1

If some of the clouds (e.g. Cloud1) are bridged to another ethernet (VMnet) you can connect your EVE lab to an external VM or physical device (like e.g. a switch, IP phone or access point).

▲ For ESXi make sure that you have set Promiscuous mode security settings on the vSwitch and Port group to Accept. Please refer to section 10.5

The next sections will explain how you can use Cloud networks in EVE to connect to other external (e.g. VMWare) VMs or physical devices.

© EVE-NG LTD Page 151 of 263



# 10.7 Connecting external VM machines to the EVE Lab

#### 10.7.1 ESXi VM machines

External ESXi VM machines can be connected to EVE labs using cloud interfaces.


**NOTE**: A single Cloud interface can be used to connect more than one external VM to the EVE lab.

**Example:** Connecting a Web Security Appliance (WSA) to the lab using the Cloud1 interface.


Step 1: Create a new or use an existing portgroup on your ESXi and assign it to EVE and WSA VMs as shown below. Make sure you have set Promiscuous mode on the vSwitch (portgroup WSA-MGMT) to Accept.

▲ NOTE: VM machines must be in a powered off state to assign network interfaces.

#### Portgroup WSA-MGMT (with vSwitch5 as parent) settings:




#### Parent vSwitch5 settings:



#### **EVE and WSA VMs settings**


© EVE-NG LTD Page 152 of 263





# EVE Lab connected to the WSA (Cloud1)

- ▲ NOTE: ESXi WSA VM obtained the IP 192.168.10.3 from the DHCP pool on the lab switch. The gateway is 192.168.10.1
- NOTE: The Firefox Docker node user for management obtained the IP 192.168.10.2 from the DHCP pool configured on the lab switch.



### 10.7.2 VMWare workstation machines

External (meaning not running inside EVE) VMWare workstation machines can be connected to EVE labs using cloud interfaces.

NOTE: A single Cloud interface can be used to connect more than one external VM to the EVE lab.

© EVE-NG LTD Page 153 of 263




**Example:** Connecting Web security Appliance (WSA) to the lab using **Cloud2** interface.


NOTE: VMs must be in a powered off state to assign network interfaces.

Step 1: Open your VMWare Workstation Virtual Network Editor and configure the VMnet interface for the Cloud and WSA VMs. If necessary add a new VMnet. The example below is showing VMnet2 Settings in VMWare workstation. DHCP must be disabled for VMnet2.

#### **Virtual Network Editor settings:**



#### **EVE and WSA VMs settings**




#### **EVE Lab connected to the WSA (Cloud2)**

- ▲ NOTE: ESXi WSA VM obtained the IP 192.168.10.3 from the DHCP pool on the lab switch. The gateway is 192.168.10.1
- NOTE: The Firefox Docker node user for management obtained the IP 192.168.10.2 from the DHCP pool configured on the lab switch.

© EVE-NG LTD Page 154 of 263





# 10.8 Connecting EVE Lab to a physical device

#### 10.8.1 ESXi EVE

To connect a physical device (e.g. router, switch) to an EVE lab over a cloud interface, we have to bridge the ESXi NICs ethernet port to a VMnet interface.

- ▲ IMPORTANT NOTE: Make sure that you have set Promiscuous mode security settings on the vSwitch and Port group to Accept.
- ▲ IMPORTANT NOTE: If you are building trunk between EVE lab node to real Switch, please make sure you have set your ESXi vSwitch interface to accept all vlans. Reference: https://kb.vmware.com/s/article/1004074

**The Example** below is showing ESXi Server settings of the virtual network bridged to the physical interface.

Logical chain of the networking bridge:

EVE Lab Cloud0 → Portgroup "Management 90 UD" → vSwitch 1→ Physical Adapter eth1


© EVE-NG LTD Page 155 of 263



#### vSwitch1 settings bridged with Server Ethernet port vmnic1 (physical adapter)




# Portgroup "Management 90 UD" Settings associated with vSwitch1



#### **EVE VM Settings**

EVE VM Cloud0 is connected to Portgroup "Management 90 UD"




#### **EVE Lab Connected to a physical device**

Physical Topology

© EVE-NG LTD Page 156 of 263



Cisco 887M device port Fastethernet 3 is physically connected to Server port eth1.



#### EVE Lab Topology

EVE lab switch port G0/0 is configured as trunk and connected to Cloud0 over bridged chain to the physical Cisco 887M Router switchport Fastethernet 3




#### 10.8.2 VMWare workstation EVE

Similar to the ESXi connection, it is recommended to have a second ethernet interface on your PC. It can be a USB ethernet extender as well. Not all ethernet adapters fully support a layer2 connectivity over it. MS Windows OS itself strips off any tags added to the packet. Even if your NIC supports 802.1q VLAN tagging, Windows 10 strips these tags off. The example below will show a Windows 10 host connected to a physical 3750G-24 switch. The Windows 10 Host has an Intel (R) PRO/1000 PT Dual port server adapter and is bridged with VMWare workstation (version 14) VMnets.

Virtual Network Editor Settings, Bridged VMnet interfaces with Real NIC Ports

© EVE-NG LTD Page 157 of 263






EVE VM Settings. Network adapter is bridged to VMnet0 (ethernet Intel Pro 1), and Network adapter 2 is bridged to VMnet1 (ethernet Intel Pro 2).

Responding cloud interfaces on EVE VM:

Cloud0→Network Adapter→VMnet0→IntelPro


Cloud1→Network Adapter 2→VMnet1→IntelPro#2




Physical connection scheme and VMware bridging.

© EVE-NG LTD Page 158 of 263





#### EVE Lab scheme.



The following solution allows Windows hosts to transmit tagged packets over ethernet. This has been used in the example above.

▲ Warning. You are making changes to your Windows registry files! This is at your own risk

 $\underline{\text{https://www.intel.co.uk/content/www/uk/en/support/articles/000005498/network-and-i-o/ethernet-products.html}$ 

### 10.8.3 Bare metal server EVE

A physical server usually has more than one ethernet port, free ports can be bridged with EVE clouds and used for external connections. EVEs internal interface settings are already bridged in order, pnet0-9 are mapped to eth0-9. Refer to the bridging table in section 10.6

```
# Cloud devices
iface eth1 inet manual
auto onet1
iface pnet1 inet manual
bridge_ports eth1
bridge_stp off

iface eth2 inet manual
auto pnet2
iface pnet2 inet manual
bridge_stp off
bridge_stp off
```

```
cat /etc/network/interfaces
```


Basically, your servers physical port eth0 is bridged to pnet0 which is Cloud0 in your labs, eth1 is bridged to pnet1 which is Cloud1 in your labs (and so on). Refer to the bridging table in section 10.6

The example below shows how to connect a bare-metal EVE server with a physical Cisco 3750E switch.

© EVE-NG LTD Page 159 of 263



# Physical connection topology:



The EVE lab switch's CDP neighbor is the 3750E switch's port Gig 1/0/25: A trunk has been configured between the EVE lab switch and the physical 3750E switch.

© EVE-NG LTD Page 160 of 263





# 11 Advanced EVE Lab features

# 11.1 Lab design objects

EVE Pro has drawing elements integrates to add drawings and text information to the lab topology. Objects can be placed on the topology in two ways.

Example below, EVE lab with design elements:





#### 11.1.1 Custom shape

There are three custom shapes that can be added to the topology: square, round square and circle (sphere).

© EVE-NG LTD Page 161 of 263



Type: Square, round square or circle

**Name**: This field can be filled with your preferred shape's name. If the field is left empty, EVE will generate a name for the shape.

Border type: Two options: line or dashed




**Border width**: Increase or decrease the width of the border. This can be edited later in the "Shape Edit" menu.

**Border colour**: Allows you to choose a colour for the shape's border. This can be edited later in the "Shape Edit" menu.

**Background colour**: Allows you to choose a colour to fill your shape with. This can be edited later in the "Shape Edit" menu.

Example: Added a circle and square on the topology. Shapes can be moved around the topology drag and drop style (click and move with mouse).



# 11.1.2 Resize square or circle objects

Move your mouse over the right bottom corner of the object until a corner symbol appears. Left click and drag your mouse to change object size or style (rectangle, sphere)




#### 11.1.3 Text

It is also possible to add text or other MS Office objects to your EVE topology. Rich HTML Office option allows you to copy texts from MS Word, Excel or Visio.




© EVE-NG LTD Page 162 of 263






Example: Excel table on topology:





Example: text objects added to the topology.

Example: Visio object added to the topology



# 11.1.4 Add picture to the topology

Custom images may be added by using HTML editor:


Step 1: Add a text object to the topology and press Image button for import.

© EVE-NG LTD Page 163 of 263






Step 2: User browse to import your image.



Step 3: Double click on object you wish to resize, then change width and height.




# 11.1.5 Custom object linking with telnet or other protocol

This feature allows you to link your eve topology object with external source. It can be web site or other protocol like Telnet to call out console for external object.

Step 1. Add the text or picture using HTML editor. Sections 11.1.3 or 11.1.4.

© EVE-NG LTD Page 164 of 263






Example: Custom icon added from MS Visio.

Step 2. Position your object in place where you want it to be.


Step 3. Highlight text or activate object.



Step 4. Use link button to assign custom protocol for your object. Example: Protocol Other, type in URL: telnet://10.1.1.10



Step 4. Tab Target, Example: Target/New Window



© EVE-NG LTD Page 165 of 263



Step 5. OK for Save.


NOTE to edit picture object assigned with link, use mouse mark area of object and it and double click on area beside object.



### 11.1.6 Line object

Line object allows you to draw and design lines on the topology.

Step 1. Add a Line object to the topology



**Width**: Increase or decrease the width of the line. This can be edited later in the "Shape Edit" menu.

**Arrow Style**: Allows you to make arrows to your Line object. Single arrow, Double arrows or no Plain. This can be edited later in the "Shape Edit" menu.

**Paint Style**: Allows you to solid or dashed style for line. This can be edited later in the "Shape Edit" menu.

**Line Style**: Allows you to choose a style Straight, Bezier, Flowchart or StateMachine for the line. This can be edited later in the "Shape Edit" menu.

**Line colour**: Allows you to choose a colour for the line. This can be edited later in the "Shape Edit" menu.

Line label: Allows you to add a label on the line. This can be edited later in the "Shape Edit" menu.

Example, Dashed, Bezier, double arrow line with label:

BGP Peer

**Positioning and moving line object.** Line object has invisible connection points at the ends. Use mouse to find that point, drag and drop move line connection point to your preferred lab location. Use mouse to move other line endpoint on lab location.

BGP Peer

To move all line, use CTRL to mark line endpoint and move line over topology to position it.

Edit Line object. Right click on line to call out edit window:



© EVE-NG LTD Page 166 of 263





### 11.1.7 Nodes connection links design

Refer Section 9.1.5

### 11.1.8 Cloning objects and overlay positions

Right click on the object you want to clone and choose "Duplicate". You can also change the object's overlay position using the "Send to Back" or "Send to front" options.



# 11.1.9 Objects Editing

Right click the object and choose "Edit" for additional options.



At the bottom of the "Topology Canvas" page, additional object options will appear



**Z-index**: Used to change the object's overlay position on the "Topology Canvas." An object with a higher numerically valued z-index will cover an object with a lower numerically valued z-indexed.

**Example**: The blue object has a z-index of -1 and the orange object's z-index is 0. Orange object is top over blue object.

**Border width**: Used to change the object's border width.

Border type: Used to change the border style of the object between solid and dashed.

Border colour: Used to change the colour of the object's border

Background colour: Used to change the background colour of the object

**Transparent:** Turns off background colour (filling) and makes the object transparent.



© EVE-NG LTD Page 167 of 263



Rotate: Used to rotate the object on the



Name: Used to change the object's name.

To save the object, press Save (green button).



# 11.1.10 Lock objects movement

The "Lock Lab" feature prevents objects from being moved around on the canvas (among other things). For more information about this feature, refer to section 8.1.14.

# 11.2 Custom design logical topology

EVE Pro includes a feature to upload your own custom topology picture and map nodes to it for easy access.


# 11.2.1 Custom design upload

Before you upload a custom picture in the lab, make sure it is in .png or jpg format with resolution 130-150x130-150 pixels.


TIP: It is best is to create a topology in the MS Visio and after convert it to the .png picture format with resolution 140x140.



Step 1: Open "Add an Object" and then "Pictures" from the left sidebar or right click on a free area on topology canvas and hit "Add Picture."



Step 2: Browse your PC for a .png or .jpg file and hit "Add".



Once the picture is added to the topology canvas, the sidebar will display a new option: "Logical maps"

© EVE-NG LTD Page 168 of 263



Step 3: Open the "Logical maps" menu item.



# Pictures window management

	Delete uploaded picture from the lab		
Ø	Image Map: Map nodes to places in the picture		
Topology	Display uploaded picture. Work with lab and custom topology		
	Zoom/unzoom uploaded custom topology		
*	Makes the window transparent to see the "Topology Canvas" behind it. Clicking again returns to the normal view.		
×	Close "Pictures" window.		


# 11.2.2 Custom topology mapping

This feature allows you to map the lab nodes to your custom topology picture.


Step 1: Open the Image Map window:



Step 2: Select a node, from the dropdown menu, that you want to map to the topology.




Step 3: Move your mouse over a node icon on the "Image Map" and click to map it. The grey circle means that the node is mapped.



Step 4: Continue mapping the rest of the nodes.

© EVE-NG LTD Page 169 of 263





Step 5: OPTIONAL. You can also add a mapping for a device external to your EVE server in order to telnet, VNC, or RDP to it. This way you can open sessions to all your devices (whether external or internal) in one place.



Change image map adding protocol, IP and port.



Step 6: Save your mapping and refresh the browser with F5.



#### 11.2.3 Delete topology or mapping

To delete a single node mapping, right click on node mapping circle and click "Delete."



To delete the entire custom topology, click delete.



# 11.3 Multi-configuration sets export feature

Eve Professional/Learning Center includes a "Multi-configuration Set" feature that allows you to save and manage multiple sets of configurations in a single lab. The "Configuration Export" and "Startup-configs" features will allow you to set these saved configurations as startup configs for your nodes when they boot.

▲ IMPORTANT NOTE: Before you start using the "Multi-configuration Set" feature, you must complete at least one configuration export.


© EVE-NG LTD Page 170 of 263





Nodes will be greyed out without the option to enable "Startupconfigs" until you complete at least one configuration export for each node.

#### Node boot order:



**NVRAM**: NVRAM is used as writable permanent storage for the startup configuration. During the boot process, the node will always check NVRAM for a saved configuration. Saving the configuration to NVRAM requires a vendor specific command. Cisco: copy run startup (wr), Juniper: commit, etc. It is MANDATORY to save a node's configuration before you can export it.

**Exported configuration**: A node configuration that has been exported from the node. It can be used to backup configurations or to set them as startup-configs.

**Wipe node**: Wiping a node will erase the NVRAM (running config) or the temporary image snapshot, depending on the type of node. Upon a successful wipe, the node will boot with the factory default configuration or the configuration included in the base image you are using. If you have the "Startup-config" feature enabled for the node, then it will boot with the chosen config set. You must wipe a node after changing certain node template settings like the image or startup-config. You also must wipe the node the first time you want to enable the "Startup-config" feature.

**Factory default configuration**: The base configuration that is applied from the manufacturer.

# 11.3.1 Supported nodes for configuration exports

Cisco Dynamips all nodes Cisco IOL (IOS on Linux) Cisco ASA Cisco ASAv Cisco CSR1000v

Cisco Nexus 9K

Cisco Nexus Titanium

Cisco vIOS L3

Cisco vIOS L2

© EVE-NG LTD Page 171 of 263



Cisco Viptela vEdge, vSmart, vBond

Cisco XRv

Cisco XRv9K

Juniper VRR

Juniper VMX

Juniper vMX-NG

JunipervQFX

**JunipervSRX** 

Juniper vSRX-NG

Mikrotik


PFsense FW

Timos Alcatel

vEOS Arista


### 11.3.2 Startup config management

#### 11.3.2.1 Global commands



Configurations can be managed via the "Startup-configs window which can be accessed from the sidebar menu while on the Topology page.

#### **Topology page, More Options:**



**Export all CFGs** – Exports all supported node configurations.

**Set nodes startup-cfg to default configset-** Sets all supported nodes to boot from the default configuration set.

**Set nodes startup-cfg to none** - Sets all supported nodes to boot from NVRAM configuration.

**Delete default configuration set.** Warning, this will delete your exported default configuration set for all nodes.

#### 11.3.2.2 Individual node commands

#### Select node, right click




Wipe: Wipes the NVRAM for a single node

Export CFG: Exports the configuration for a single node

© EVE-NG LTD Page 172 of 263



### 11.3.2.3 Multiple selected nodes commands



Wipe Selected: Wipes the NVRAM for selected nodes

Export all CFGs: Exports the configuration for selected nodes


Set nodes startup-cfg to default configs set: Set selected nodes to the default config set

**Set nodes startup-cfg to none**: Set nodes to boot from NVRAM or from factory default if wiped.

Delete nodes startup cfg: Delete selected node's startup cfg. (clean default set)

### 11.3.2.4 Startup-configuration window


No configuration exports or manual configs loaded for nodes



Startup-configs are exported and the "Configuration Export" feature can be used.



# 11.3.2.5 Startup-config window information



© EVE-NG LTD Page 173 of 263



<b>№</b> R1	No configuration is available for node. Grey node
№ R1	Configuration is available and can be used. Blue node. Exported configuration persist
₹ R2 OFF	Configuration persist but it is disabled. Node will boot from NVRAM or factory default if it is wiped
<b>№</b> R1 <b>4</b> ON	Configuration persists and node will boot from the configuration after being wiped
CONFIG SET  Remor Rame  Add Cassel	Add new config set.
CONFIG SET  **Ranne**   **Riche named    **Total Cancel**  **Total	Rename config set. The Default Config Set cannot be renamed.
<b>★</b> Config Set [P Addressing ✓	Select a Config Set and delete it. You cannot delete the Default Config Set. The Default configuration set can be cleaned using the sidebar / More options / Delete default configuration set
±	Upload configuration set from your local PC
4	Download configuration set to your Local PC
,	Apply Config Set button: Sets all nodes to boot from the chosen config set.
•	Config Reset button: Sets all nodes to boot from none. Node will check boot order. If the Wipe function is used, nodes will boot from factory default.
SW1 CI LLAR configuration change at 1952:1 version 15.4 service times tamps debug datatime i	Individual node export or import configuration. Configuration export/import file format is .txt.

© EVE-NG LTD Page 174 of 263






Ace Editor. Different vendor configuration edit option. Just Text visual format.

# 11.3.3 Export Default configuration set

NOTE: The default configuration set is hardcoded. It is mandatory to export a nodes configuration you can start building custom configuration sets.

#### **Example:**




Step 1: MANDATORY: Configure your nodes and make sure you applied the vendor specific command to save the running configuration to NVRAM. If you do not save the configuration, it will not be exported and in the notification area, you will receive an error message stating the node cannot be exported.

In this example the nodes have been configured with hostnames only and the configurations have been saved to NVRAM.

Step 2: Chose any method to export configurations to the Default Config Set. You can use export a single node, a group of nodes, or all nodes. Only supported nodes configurations will be exported.

Step 3: In the example below a group of nodes were selected to export configurations.





Default configuration set is completed. The notification area will display "Export All: done" when complete.

NOTE: you can configure your nodes with your preferred configuration and make it the default configuration set.


© EVE-NG LTD Page 175 of 263



# 11.3.4 Boot nodes from exported Default config set

#### Step 1: Stop all nodes

Step 2: Open sidebar and click Startup-configs. Make sure your config is set to default and the nodes config switch is green (switch on/off beside node). Press the green "Apply Config Set" button (Set all nodes to selected config set) and all your nodes will boot with the default config set after wiping them.



Step 3: Wipe nodes. For more information refer to section 9.1.3


#### Step 4: Start nodes

# 11.3.5 Export new custom config set


This section will describe how to create a new custom configuration set for the same example above.

▲ Make sure your nodes are running and booted from the default set.

Step 1: Create new custom named (e.g. "IP Addressing") configuration set, Press Add new config set.



Name it and press Add.



The new configuration set is created.

▲ NOTE: It will duplicate the default configuration set under your IP Addressing config

Step 2: Select newly created Config set IP Addressing and hit the green confirm button (Set all nodes to selected config set) on the right.

© EVE-NG LTD Page 176 of 263





Step 3: Make sure your nodes have the Startup-config slider switched to "ON" and verify the config set menu has the "IP Addressing" set selected.




Step 4: Return back to your lab and continue configuring nodes until your preferred configuration is complete. In this Example, the IP addresses are configured on the nodes.

Step 5: IMPORTANT: YOU MUST save the configuration on all nodes, even if the configuration was not changed.

Step 6: Use any method (individual, group or all) to export the new configurations to the IP Addressing set.

Step 7: You can verify that the configs were exported by re-opening the "Startup-config" window.

Make sure the correct config set is selected, and check if the configuration is exported for the node or nodes.



Repeat steps 1-7 of this section for the next configuration set.

#### 11.3.6 Edit exported configurations

It is possible to edit your configurations for the nodes manually.


Step 1: Select a config set and apply it with the green confirm button (Set all nodes to selected config set) on the right.



Step 2: Select the node you want to edit the configuration of and make your changes. Click "Save" when you are finished.

© EVE-NG LTD Page 177 of 263





Step 3: Apply the config set to all nodes with the green "Apply Config Set" button on the right (Set all nodes to selected config set).



NOTE: you can manually copy/paste any configuration into the config set editor and apply it to your node. Make sure your configuration interfaces match the lab node's interface names.

# 11.3.7 Set lab to boot from config set

To set your lab nodes to boot from the exported configuration, follow the steps below:

Step 1: Wipe nodes. Refer to section 11.3 for information about wiping nodes and the order of operations during boot.

Step 2: Open the "Startup-configs" window from the left sidebar.

Step 3: Select your preferred config set and apply it by pressing the green "Apply Config Set" button on the right (Set all nodes to selected config set).



Step 4: Start nodes.

#### 11.3.8 Set lab to boot from none

To reset your lab nodes' configuration to factory default follow the steps below:

Step 1: Wipe nodes. Refer to section 11.3 for information about wiping nodes and the order of operations during boot.

Step 2: Open the "Startup-config" window from the left sidebar

Step 3: Press the red "Config Reset" button on the right (Set all nodes to no startup-config).




Step 4: Start nodes

© EVE-NG LTD Page 178 of 263



# 11.3.9 Delete a config set

Select the config set you want to delete and click the "Delete" button. You cannot delete the default config set.



# 11.3.10 Rename a config set

Step 1: Select the config set you want to rename. Change the name and hit "Save." You cannot rename the default config set.



# 11.3.11 Export a config set to your local PC

It is possible to export configuration sets to your local PC.

Step 1: Select the config set you wish to export.



Step 2: Save it on your local PC.

NOTE: You can open this archive and edit your node configs manually. Archived configs are saved in txt format. After editing you can archive it back to .zip format and import it in EVE.


# 11.3.12 Import config set from local PC.

It is possible to import config sets to your lab.



© EVE-NG LTD Page 179 of 263





Browse to the file on your PC, select the archive or config set and upload it.

Uploaded config sets without a Name will appear in the config set menu with the name "Import". To rename config sets, refer to section 11.3.10

### 11.3.13 Export a single nodes config to your local PC

Open the "Startup-configs" window from the Side bar. Select the node that you want to export the configuration of and click the "Export" button.



# 11.3.14 Import a single nodes config from your local PC

Open the "Startup-configs" window from the sidebar. Select the node that you want to import the configuration to and click the "Import" button. Browse to the file on your local PC and click "Upload."



**NOTE**: The configuration must be in txt file format.

# 11.3.15 Set lab nodes to boot from different config sets

The "Multi Configuration set" feature allows you to set nodes to boot from different config sets in the same lab.


Option 1: Open the "Nodes" list from the left sidebar. Choose your node and select a config set from the dropdown. Stop the node, wipe it and start it again. Your node will boot from the selected config set.

© EVE-NG LTD Page 180 of 263





Option 2: Stop the node, right-click on the node and click "Edit." Select your preferred config set for the node and click "Save."



#### 11.3.16 Lab config script timeout

Lab config script timeout is used when nodes are waiting to boot from a config set. The node will literally wait during boot until the configuration is applied from the config set.

Hit "More actions" and then "Edit lab" from the sidebar. Set the config script timeout in seconds. By default, this timer is set to 300 seconds for new labs.



#### 11.4 Lab Timer

For self-controlled lab timing, EVE Pro has integrated a "Lab Timer" feature.

#### 11.4.1 Set the Lab Countdown Timer

Step 1: Click "More Options" and then "Edit Lab" from the sidebar.

Step 2: Set the "Lab Countdown Timer" in seconds for the time you wish to display on the topology and confirm by clicking "Save". 7200 seconds = 120 minutes.



Step 3: To start your lab, be sure all nodes are running.

Step 4: Hit "Lock Lab" from the sidebar. A red sign means that the lab is locked.



Step 5: When ready to start, click "Refresh Topology" from the sidebar. The countdown timer will be displayed on the "Topology Page" in the top left corner.

© EVE-NG LTD Page 181 of 263



#### 11.4.2 **Stop the Lab Countdown Timer**

Step 1: Click "Unlock Lab" Grey means that the lab is unlocked.



Step 2: Hit "Refresh Topology" from the sidebar

▲ NOTE: The lab timer does not stop nodes or disconnect sessions from the lab.

#### 11.5 Lab Tasks

Lab task or workbook creation feature.


#### 11.5.1 Creating a new simple task

Step 1: On the side bar click on "Lab Task(s)" to open the Lab Task(s) management window.



Step 2: Click on the "+" sign to create a new task. Enter the name of the task name and click on "Add" to create the task.





#### 11.5.2 Edit a simple task


Step 1: Press the edit button next to the name of the newly created task.



Step 2: Use the rich text editor Window to create your Task / Workbook. It is a recommended option to copy/paste task content from MS Word. Save your Task content by clicking on the "Save" button.


Page 182 of 263 © EVE-NG LTD





### 11.5.3 Create a multi tabs task (task on multiple tabs/pages)

Step 1: Click on the "+" sign to create a new task. Enter the name of the task name and click on "Add" to create the task.



### 11.5.4 Edit a multi tabs task (task on multiple tabs/pages)


Step 1: Press the edit button next to the name of the newly created task.




Step 2: Click on the "Insert tabs" button.

© EVE-NG LTD Page 183 of 263






Step 3: Enter the name of your new task group and choose the number of tabs (must be between 2 and 9). Tab names can be changed later.



Step 4: To save your your tabbed task, press "Save".



### 11.5.5 Edit tabs (Multi tabbed task).


Step 1: Activate the tab for which you want to edit its content and press the edit button.

© EVE-NG LTD Page 184 of 263






Step 2: Rename your tab,



Step 3: Press the "Show Blocks" button, this will help find the right place to create the task tab content. Make sure that you are copying or creating the tabbed task content into the correct place (Tab 1 Content)

NOTE: It is strongly recommended to use "full screen" for the rich html text editor when you are working with tabbed tasks. Press the "full screen" button to work with tasks. Press it again to exit full screen mode.




Step 4: Save your modified task by clicking on "Save". To edit another tab, repeat steps 1-3.

### 11.5.6 Create a task with your PDF workbook

Step 1: create new Task and name it and press Add:

© EVE-NG LTD Page 185 of 263






Step 2: Press edit Task and locate PDF button, Press it



Step 3: Navigate to your pdf document, Press OK.



Step 4: To view your uploaded book, use, Side Bar/Tab Tasks/your taskname



© EVE-NG LTD Page 186 of 263




### 11.5.7 Create a task with Online document (PDF or HTML)

Online document or web site task (https ONLY, iFrame allowing use Secure http only)


Step 1: Have ready your link to online web site or document. Example:

https://www.eve-ng.net/images/EVE-COOK-BOOK-latest.pdf

Step 2: create new Task and name it and press Add:





Step 3: Press edit Task and locate iFrame button, Press it



Step 4: Type the path to your online document, set Width to 100%, and Height resolution to 10000.

The path location is <a href="https://www.eve-ng.net/images/EVE-COOK-BOOK-latest.pdf">https://www.eve-ng.net/images/EVE-COOK-BOOK-latest.pdf</a>, which prepared in Step 1. Press OK for iFrame properties and Save Task, Press Save






© EVE-NG LTD Page 187 of 263



Step 5: To view your uploaded book, use, Side Bar/Tab Tasks/your taskname



### 11.5.8 Delete a task

Step 1: From the Side bar click on "Task Management":



Step 2. Click on the delete symbol next to the task name which you want to delete.



© EVE-NG LTD Page 188 of 263



# 12 Wireshark capture

All EVE-NG Professional and Learning Centre console types have the integrated Wireshark capture feature. This means that it is not necessary to have Wireshark installed on the client machine you are using to access EVE with.


EVE-NG Professional currently supports ethernet interface capturing only.


### 12.1 Native Console Wireshark capturing

Step 1: Right click on the node you wish to capture, choose "Capture" and then the relevant interface. The capture will open in an HTML session. EVE-PRO supports capture for ethernet and serial interfaces.

Select the interface frame type which will be captured:

- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.






Step 2: To save the captured file to your client PC, stop the capture and choose File/Save As

© EVE-NG LTD Page 189 of 263





Step 3: Choose the location where you want to save the captured file

#### **IMPORTANT**:

#### /nobody/thinclient\_drives/GUACFS/Download


Enter a name for your captured file and press Save. Your browser will offer to download your capture fil and save on your local PC. Refer Section 12.2

## 12.2HTML5 Console Wireshark capturing

Step 1: Right click on the node you wish to capture, choose "Capture" and then the relevant interface. The capture will open in an HTML session. EVE-PRO supports capture for ethernet and serial interfaces.


Select the interface frame type which will be captured:

- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.




© EVE-NG LTD Page 190 of 263





Step 2: To save the captured file to your PC, stop the capture and choose File/Save As



Step 3: Choose the location where you want to save the captured file


#### **IMPORTANT**:

© EVE-NG LTD Page 191 of 263




### /nobody/thinclient\_drives/GUACFS/Download

Enter a name for you captured file and press Save.



Step 4: A window will open that will allow you to save your captured file on your client PC. If the client PC's browser is set to download automatically, your captured file will be saved in the default browser download folder.



© EVE-NG LTD Page 192 of 263





## 12.3 HTML5 Desktop Console Wireshark capturing

Step 1: Right click on the node you wish to capture, choose "Capture" and then the relevant interface. The capture will open in an RDP session. EVE-PRO supports capture for ethernet and serial interfaces.


Select the interface frame type which will be captured:

- Ethernet for Ethernet, Fast Ethernet, Gigabit Ethernet.
- Serial interface frames: HDLC, PPP or Frame Relay.






Step 2: Stop capturing with the STOP button.



Step 3: Chose File/Save As



© EVE-NG LTD Page 193 of 263




Step 4: Chose the path to save the captured file,


#### **IMPORTANT**:

/nobody/thinclient\_drives/media/nobody/thinclient\_drives/GUACFS/Download/

Enter a name for captured file. Press Save.



Step 4: A window will open that will allow you to save your captured file on your client PC. If the client PC's browser is set to download automatically, your captured file will be saved in the default browser download folder.



© EVE-NG LTD Page 194 of 263



# 13 Thinclient File Exchange

NOTE: Thinclient file exchange feature is available for HTML5 or desktop HTML5 consoles only. Make sure you are logged in EVE with one of it.


The Thinclient file exchange feature allows you to transfer files between your native client workstation and the integrated Docker Desktop. It is used when managing EVE via HTML5 consoles. This feature eliminates the need for file transfer software on your client workstation and makes it very easy to import/export labs or download Wireshark captures.

### 13.1 Thinclient files downloading

The Thinclient file exchange feature allows you to download files from your EVE Server over an HTTP/HTTPS session to your client PC. Examples below will show you how to download exported lab files. This feature is not restricted to just lab files or Wireshark captures. It can be used to download or upload any miscellaneous files you may need.

Example: HTML5 console to server-gui Docker node: We want to export our test.txt file and download it to our client PC over HTML5.






Step 2: Navigate to the desktop of the HTML5 server-gui station and double click **thinclient\_drives** and navigate to: **thinclient\_drives/GUACFS/Download/** 


Step 3: Drag and drop the test.txt file from right to left.

© EVE-NG LTD Page 195 of 263





Step 4: A window will open that will allow you to save your captured file on your client PC. If the Native PC's browser is set to download automatically, your selected file will be saved in the browsers default download folder.



**NOTE:** Please refer to section 12 for downloading Wireshark capture files from EVE HTML5 consoles.

## 13.2 Thinclient File upload


Sometimes it is necessary to upload files to your EVE labs. The Thinclient file exchange feature allows you to upload files from your client PC to the EVE HTML5 server-gui station. The

© EVE-NG LTD Page 196 of 263




example below will show you how to upload a text file to the EVE HTML5 server-gui station. Any other files can be uploaded the same way.

Step 1: Adjust your browser so that you can see it and the file that you want to transfer.




Step 2: On the EVE HTML5 Desktop navigate to: **thinclient\_drives/GUACFS/** and drag and drop the file from your client PC to opened location on HTML5 Desktop.




Step 3: Next you will see a notification in the bottom right corner.

© EVE-NG LTD Page 197 of 263





Step 4: To finish the operation and see the uploaded file in the HTML desktop station, press the refresh button. Our Text file SW.txt has been uploaded.



# 13.3 Other Thinclient file operations


Files that have been uploaded via the thinclient feature can also be transferred to nodes inside your EVE labs via TFTP. In the example below we have uploaded a config file (sw.txt) and would like to transfer it to node R1.

Step 1: Add the **eve-gui-server** docker node to your lab and edit its settings. Set the console type to RDP and configure the IP address settings (DHCP or static) accordingly so that the


© EVE-NG LTD Page 198 of 263



docker node can reach the destination node (R1 in this example). For Docker IP addressing please refer to section 14



Step 2: Click on the **eve-gui-server** docker node to open an RDP session.




Step 3: Open the **thinclient\_drives** location where you uploaded your file to:


/thinclient\_drives/media/nobody/thinclient\_drives/GUACFS/

Next, drag and drop your file to the desktop folder named TFTP.


© EVE-NG LTD Page 199 of 263







Step 4: Open the destination node's (R1) console and use the tftp command to copy your file:



© EVE-NG LTD Page 200 of 263



© EVE-NG LTD Page 201 of 263



### 14 Dockers

### 14.1 EVE integrated docker stations

EVE-NG Professional and Learning Centre edition have integrated Docker stations that allows your server to use its resources more efficiently. Dockers offer the advantage of not having to duplicate processes already running on the host system. With a Docker, you run only the processes you need for the hosted application. In comparison, virtual machines have to run a complete guest operating system, including many of the same processes that are already running on the server host.

⚠ IMPORTANT NOTE: EVE Docker stations for html console access are using network 172.17.0.0/16. Please avoid use this network on the EVE management or other clouds or interfaces.

#### 14.1.1 Docker Machines

#### eve-gui-server (default)

- Fully featured Linux workstation with integrated Thinclient. For more information on the Thinclient operation please refer to section 13.
- napalm
- ansible
- python
- RDP console
- DHCP or Static IP address
- WWW Server (web page home directory www is located on desktop)
- TFTP Server (for access to TFTP server, root/eve or nobody/eve, home directory TFTP is located on desktop)
- FTP server (for access to FTP server, root/eve, home directory for ftp is root)
- Java Integration for ASDM access to Cisco ASA/IPS. For access to ASDM where Java is required, please follow this reference link:

https://192.168.100.5/admin/public/asdm.jnlp

Where 192.168.100.5 is the ASA IP for ASDM connection


NOTE: Older ASA require to configure extra SSL encryption to communicate with Java on the docker station. ASA 9.1.5 CLI:

ssl encryption aes256-sha1

**Example**: Access to ASAv ASDM from Docker server-gui station

© EVE-NG LTD Page 202 of 263





#### eve-firefox (default)

- A Docker for hosting a Mozilla Firefox browser. Useful for accessing another nodes management interface using http or https. The browser already has Java integrated so that you can utilize GUIs that require it, like ASDM for Cisco's ASA.
- RDP console
- DHCP or Static IP address

#### eve-wireshark (default)

- Fully featured Wireshark workstation with integrated Thinclient. For more information on the thinclient operation please refer to section 13.
- RDP console

#### eve-chrome (extra install, section 14.5)

- A Docker for hosting a Google Chrome browser. Useful for accessing another nodes
  management interface using http or https. The browser already has Java integrated so
  that you can utilize GUIs that require it, like ASDM for Cisco's ASA.
- DHCP or Static IP address

#### eve-kali-large (extra install, section 14.5)

- A Docker for hosting a Kali Linux. Fully featured Security vulnerability and penetration test machine
- DHCP or Static IP address
- Java Integration for ASDM access to Cisco ASA/IPS. For access to ASDM where Java is required, please follow this reference link:
- https://192.168.100.5/admin/public/asdm.jnlp
- Where 192.168.100.5 is the ASA IP for ASDM connection


© EVE-NG LTD Page 203 of 263





#### eve-ostinato (extra install, section 14.5)

- A Docker for hosting a Ostinato 0.9 GUI. Fully featured Ostinato 0.9 packet generator and network traffic generator machine
- DHCP or Static IP address
- Fully featured Ostinato GUI



### 14.1.2 Docker DHCP IP address setup

EVE integrated Docker stations have two options for setting an IP address.


© EVE-NG LTD Page 204 of 263



#### **DHCP IP address option.**

Step 1: Add the node to the topology and make sure the DHCP option is **enabled** under the edit node window. Refer to section 14.2 for the correct console type.

Step 2: Ensure the docker's DHCP request can reach a DHCP server either in your lab or externally through a Cloud Network like Cloud0.



### 14.1.3 Docker Static IP address setup

Step 1: Add the node to the topology and make sure the DHCP option is **disabled** under the edit node window Reference section 14.2 for the correct console type.


Step 2: On the left sidebar menu open Startup-config and use the example syntax below to set the ip for your Docker node. Make sure you are using the exact syntax for your static IP setup:

```
# Set ip address and Default route
ip addr add 10.100.100.103/24 dev eth0 || true
ip route add default via 10.100.100.1 || true

# Set DNS server
cat > /etc/resolv.conf << EOF
nameserver 8.8.8.8
EOF</pre>
```

© EVE-NG LTD Page 205 of 263





Step 3: Press the Save button below and switch the node to boot from the startup-config.

### 14.1.4 Docker multi interfaces setup

Step 1: Add the node to the topology and make sure the DHCP option is **disabled** under the edit node window Reference section 14.2 for the correct console type.

Step 2: On the left sidebar menu open Startup-config and use the example syntax below to set the ip for your Docker node. Make sure you are using the exact syntax for your static IP setup. It is recommended to add static routes under interfaces to reach specific networks if required.

```
# Set ip address eth0
ip addr add 192.168.1.200/24 dev eth0 || true
ip route add default via 192.168.1.1 || true

# Set ip address eth1
ip addr add 172.16.1.201/24 dev eth1 || true
# Set static route for eth1
ip route add 10.100.100.0/24 via 172.16.1.1 dev eth1 || true

# Set ip address eth2
ip addr add 10.1.1.10/24 dev eth2 || true
# Set static route for eth2
ip route add 10.10.10.0/24 via 10.1.1.1 dev eth2 || true
# Set DNS server
cat > /etc/resolv.conf << EOF
nameserver 8.8.8.8
EOF</pre>
```

#### 14.1.5 Docker server-gui custom WEB page

Step 1: Add the node to the topology and make sure the DHCP option is **disabled** under the edit node window Reference section 14.2 for the correct console type.

© EVE-NG LTD Page 206 of 263




Step 2: On the left sidebar menu open Startup-config and use the example syntax below to set the ip and html page for your Docker node. Make sure you are using the exact syntax for your static IP setup and custom HTML values:

```
# Set ip address and Default route
ip addr add 10.100.12.100/24 dev eth0 || true
ip route add default via 10.100.12.10 || true
# Set DNS server
cat > /etc/resolv.conf << EOF</pre>
nameserver 8.8.8.8
EOF
# Create a Default web page
# Use 'EOF' do avoid variable from expanding
# Delete default index page
rm /var/www/html/index.html || true
# Create a Default web page
# Use 'EOF' do avoid variable from expanding
cat > /var/www/html/index.php << 'EOF'</pre>
<center>
<?php
echo gethostname();
?>
<hr>>
       width="596" height="239" src="data:image/png;base64,---
imagecode ommittedg==">
<hr>
<?php
//whether ip is from share internet
if (!empty($ SERVER['HTTP CLIENT IP']))
    $ip address = $ SERVER['HTTP CLIENT IP'];
//whether ip is from proxy
elseif (!empty($_SERVER['HTTP X FORWARDED FOR']))
    $ip address = $ SERVER['HTTP_X_FORWARDED_FOR'];
//whether ip is from remote address
else
    $ip address = $ SERVER['REMOTE ADDR'];
echo 'Client Address: '.$ip address;
?>
</center>
EOF
```

© EVE-NG LTD Page 207 of 263





Step 3: Press the Save button below and switch the node to boot from the startup-config.





© EVE-NG LTD Page 208 of 263



### 14.2 Docker Consoles

To set consoles for EVE Docker stations, right click on node and click Edit. Set the required console type





Docker Station	Console type
eve-gui-server (napalm, ansible)	RDP
eve-chrome (optional)	RDP
eve-wireshark	RDP
eve-firefox	RDP
eve-kali (optional)	RDP
eve-kali-large (optional)	RDP
eve-ostinato (optional)	RDP

# 14.3 Docker cli root access

All EVE docker stations have the following configured CLI root account.

**Username: root** 

© EVE-NG LTD Page 209 of 263



#### Password: eve

⚠ NOTE: The root login for SSH can be commented in sshd file. Use vi to edit and remove comment "#" for PermitRootLogin

vi /etc/ssh/sshd\_config
PermitRootLogin yes

Regular user (root user) SSH access to EVE Docker:


**Username: nobody** 

Password: eve

### 14.4 Dockers re-install/update

To install or fix docker stations in the EVE Pro issue the following commands from the CLI of EVE.

When dockers are properly installed, your EVE CLI command dc images output must show:



If you still see some docker line with <none>

root@eve-ng:~# dc imag  REPOSITORY	TAG	IMAGE ID	CREATED	SIZE
<none></none>	<none></none>	cc286e6ac274	16 seconds ago	1.87GB
eve-qui-server	latest	f3aa6e0e9a56	3 minutes ago	3.04GB
eve-wireshark	latest	638ed7cf5b80	12 minutes ago	887MB
eve-firefox	latest	259293d73b07	13 minutes ago	1.49GB
eve_deekton	latest	78e9c2e618a5	15 minutes ago	2 79GB

please use reinstall dockers command:

```
apt install --reinstall eve-ng-dockers
```

Reference for Dockers reinstall and upgrade: <a href="http://www.eve-ng.net/documentation/eve-ng-upgrade">http://www.eve-ng.net/documentation/eve-ng-upgrade</a>

### 14.5 Extra docker packages

NOTE: Not included in the default EVE Pro installation. This can take some time depending on your Internet connection and disk speed.

Kali Linux Full, to install issue command:

```
apt update
apt install eve-ng-kali-large
```

Chromium Linux http, to install issue CLI command:

```
apt update
```

© EVE-NG LTD Page 210 of 263



apt install eve-ng-chrome

Ostinato docker, to install issue CLI command:

```
apt update apt install eve-ng-ostinato
```

Docker-in-docker (DinD) docker. This docker is dedicated for complex docker stacks. Refer section: **14.6.2**. To install issue CLI command:

```
apt update
apt install eve-ng-dind
```

To verify Installed dockers, issue CLI command

<pre>dc images root@eve-ng:~# dc i</pre>	mages			
root@eve-ng:~# dc 1 REPOSITORY eve-dind eve-gui-server eve-kali-large eve-wireshark eve-firefox eve-ostinato eve-desktop dockergui-rdp root@eve-ng:~#	mages TAG latest	IMAGE ID 6e067b53b145 0c764bb836f9 6982b7fa25e1 413aae02d43d 8882ac260c1f 63497fd2da4d b041a187ded9 be03f3b46439	CREATED  3 days ago 2 months ago 2 months ago 4 months ago	SIZE 747MB 3.69GB 11.8GB 1.62GB 2.15GB 1.79GB 3GB 1.29GB

### 14.6 Third parties dockers

Starting EVE-NG Pro version 2.0.6-52, the third party dockers can be installed on the EVE. However, some limitation still exists. You are free to evaluate by yourself if a specific one is working.

Two main categories of dockers require each a specific method for EVE integration:

- Simple Docker
- ❖ Docker's Stack

#### 14.6.1 Simple docker installation

Simple docker is the classic docker running in a standalone mode. You could find large choice of docker images on https://hub.docker.com or create the Docker by yourself.

Complete guide about dockers can be found on https://docs.docker.com/

Note: Internet access is a must. For simple docker, you only have to use:

```
dc pull <dockername>
```

Note: "dc" is EVE-NG alias for docker -H tcp://127.0.0.1:4243 which simplify docker operations in the EVE.

Once your new docker is pulled, you are able to use it in EVE-NG topologies. EVE-NG will start it using correct parameters automatically.

Example: SSH to your EVE. Install adosztal AAA docker:


root@eve-ng:~# dc pull adosztal/aaa

© EVE-NG LTD Page 211 of 263



root@eve-ng:~#	dc images			
REPOSITORY	TAG	IMAGE ID	CREATED	SIZE
eve-dind	latest	6e067b53b145	3 days ago	747MB
adosztal/aaa	latest	862d42a1c8f5	8 weeks ago	311MB
eve-gui-server	latest	0c764bb836f9	2 months ago	3.69GB
eve-kali-large	latest	6982b7fa25e1	2 months ago	11.8GB
eve-wireshark	latest	413aae02d43d	4 months ago	1.62GB
eve-firefox	latest	8882ac260c1f	4 months ago	2.15GB
eve-ostinato	latest	63497fd2da4d	4 months ago	1.79GB
eve-desktop	latest	b041a187ded9	4 months ago	3GB
dockergui-rdp	latest	be03f3b46439	4 months ago	1.29GB
root@eve-ng:~#				

New docker use: Open a new lab, add docker and select adosztal/aaa with console in tenet mode.



#### 14.6.2 Docker stack installation

Docker's Stack is a complex structure of multi intercommunicating dockers. For example, a Web service docker is using another Database Docker service.

To avoid involve EVE host internal process and network, the new add-on docker is provided: "eve-dind". This add-on is a dedicated docker container allowing to build complex stack. The classic method is based on docker-compose.

The example below illustrates how to build complex docker LibreNMS, Network Management System.

Note: Internet access is a must. SSH to your EVE as root.

#### Sample:

Step 1: On eve cli, type:

```
apt update
apt install eve-ng-dind
```

Note: install eve-ng-dind add-on docker and is required only once.

© EVE-NG LTD Page 212 of 263



#### Step 2: Create a new lab

Step 3: Add on the lab:

- a. NAT network
- b. Docker eve-dind (set console to 'telnet' and enable dhcp)
- Step 4: Connect docker to NAT network
- Step 5: Start Docker
- Step 6: Open Docker Console
- Step 7: Type in console:

```
git clone https://github.com/librenms/docker.git librenms-src

cp -r librenms-src/examples/compose librenms

rm -fr librenms-src

cd librenms

docker-compose up -d
```

#### Commit your created docker with new name.

Step 8: Open a cli access to your EVE server

Step 9: Type within the EVE cli:

Find your current running container ID using eve-dind image

dc ps -a

- Step 10: IMPORTANT: On the Lab UI stop docker. Do not wipe, but stop.
- Step 11: Commit your created docker with custom name.


```
dc commit <containerid> eve-librenms
```

Step 12: On LAB UI: Stop all nodes, Close Lab, Delete Lab

Note, when you add newly created docker in lab, use vendor advised settings, x4 CPU and 8GB Ram for librenms docker. Console: Telnet. Graphic Interface https.

© EVE-NG LTD Page 213 of 263






### 14.7 Customize docker image with your own changes.

#### Step 1. Connect your existing docker node to the internet

Sometimes you may have your own packages to be installed on the docker and kept for future labs. For this connect your docker to the Internet. It can be achieved connecting docker to Management Cloud0 or NAT cloud. **Example below**, Sever-gui docker is connected to Cloud NAT.



Step 2. Make your installs, packages. Example:

In the screen above I did install genisoimage package

© EVE-NG LTD Page 214 of 263



apt install genisoimage

Step 3. Obtain your RUNNING docker container ID:

From EVE CLI issue command:

dc ps

Step 4. Commit your prepared docker image with new name. example below I called it evegeniso

dc container commit <containerid> <newimagename>

```
dc container commit 0d4b3f8c314c eve-geniso
```

Step 5 check if new Docker image is created

dc images

```
root@eve-n
REPOSITORY
                                                        IMAGE ID
                                                                                                                 3.19GB
4.77GB
3.95GB
1.34GB
3.11GB
                                                        e6dd56c3b26c
d1fda568e8a0
eve-geniso
                            latest
eve-ǩali
                                                        f2a7a3d6a423
e89cad6b1813
eve-nso
                            latest
eve-ostinato
                            latest
                                                                                     2 months ago
                                                                                     3 months ago
                                                        a13cb401c8dd
                            latest
eve-qui-server
eve-firefox
                                                                                                                 1.49GB
                                                        8900664e9f3b
                            latest
                                                                                    4 months ago
7 months ago
                            latest
eve-wireshark
                            latest
                                                                                                                 888MB
eve-desktop
dockergui-rdp
                                                                                                                 2.39GB
553MB
                                                        a65b62fa69b6
                            latest
                                                                                       months ago
phusion/baseimage
root@eve-ng:~#
                                                        877509368a8d
                                                                                                                 225MB
                                                                                       years ago
```

Step 6. Optional, If you want to keep this image and later load in other EVE installs, then you must create exportable .tar image.

```
dc image save -o /root/mysuperimage.tar <image name>
```

Step 7 Optional, upload your .tar file in new EVE root, and install it in Dockers location.

```
dc image load -i /root/mysuperimage.tar
```

## 14.8 Delete docker image from EVE

Step 1. From EVE CLI issue command to check docker ID to be removed.

dc images

```
root@eve-ng:~# dc images
REPOSITORY TAG IMAGE ID CREATED SIZE
eve-geniso latest e6dd56c3b26c 4 seconds ago 3.19GB
eve-kali latest d1fda568e8a0 3 weeks ago 5.97Ge8564.77GB
eve-nso latest f2a7a3d6a423 8 weeks ago 3.95GB
eve-ostinato latest e89cad6b1813 2 months ago 1.34GB
eve-gui-server latest a13cb401c8dd 3 months ago 3.11GB
eve-firefox latest 8900664e9f3b 4 months ago 1.49GB
```

© EVE-NG LTD Page 215 of 263



Step 2. Use command: dc rmi -f <id of docker image>.

dc rmi -f e6dd56c3b26c

Step 3. Check with **dc images** if docker is removed.

Step 4. Finish removal with **apt remove --purge eve-ng-kali**, where eve-ng-kali is your docker repository name.

© EVE-NG LTD Page 216 of 263



# 15 EVE Cluster System

The EVE-NG cluster refers to a group of EVE-NG nodes working together as a single entity to provide users with better scalability and availability.

The EVE-NG cluster model is designed to work as a one + many systems, the EVE-NG management server is acting as "Master" node, EVE-NG installations as "Satellite" can be members of this cluster.

One "Master" EVE-NG can have several satellites joined into its cluster but each satellite can only be joined to one Cluster/Master.


Any existing EVE-NG Pro installation is already a EVE-NG "Master", cluster members will need to be installed as "satellite" and can then easily be joined.

## 15.1 EVE Cluster design models

#### 15.1.1 Bare metal servers cluster

#### Design 1 EVE-NG Cluster Bare HW servers, recommended


EVE Cluster 208 vCPU, 896GB RAM, 16TB SSD. Cluster members can be different HW configuration. The 1GB LAN connection or better is required



#### 15.1.2 ESXi Virtual Machines cluster

#### Design 2 EVE-NG Cluster VM Ware ESXi Virtual Machines

 $EVE\ Virtual\ ESXi\ Cluster\ 112\ vCPU,\ 384GB\ RAM,\ 8TB\ SSD.\ Cluster\ members\ can\ be\ different\ VM\ configuration\ and\ located\ on\ same\ or\ different\ ESXi\ servers$ 




© EVE-NG LTD Page 217 of 263



## 15.1.3 Hybrid cluster

#### Design 3 Hybrid EVE-NG Cluster Bare metal and VM Ware ESXi Virtual Machines


EVE Hybrid Bare HW and ESXi Cluster 120 vCPU, 384GB RAM, 6TB SSD. Cluster members can be different VM configuration and located on same or different ESXi servers



## 15.1.4 VM Ware workstation light cluster

# Design 4 Light EVE-NG Cluster Desktop PCs and Wifi Laptop with VM Ware workstation and Virtual Machines


Light EVE Cluster with Desktop PCs and Laptop Wifi.



## 15.1.5 Google Cloud cluster

# Design 5 EVE-NG Cluster Desktop PCs VM Ware workstation VM and Google Cloud VMs

High speed internet is required



© EVE-NG LTD Page 218 of 263



# 15.2 EVE Cluster pre-requisites

#### 15.2.1 Firewall rules between Master and Satellite nodes

Node	Protocol	Port	Direction	Source	Destination
MASTER	TCP	22	ingress and egress	MASTER node IP	SATELLITE nodes IPs
MASTER	UDP	all	ingress and egress	MASTER node IP	SATELLITE nodes IPs
SATELLITE	ТСР	22	ingress and egress	SATELLITE node IP	MASTER Node IP
SATELLITE	UDP	all	ingress and egress	SATELLITE node IP	MASTER Node IP

## 15.3 EVE Cluster Member's hardware requirements

Any suitable Hardware or virtual device. Please refer Chapter 2

## 15.4EVE Cluster MASTER Node Installation

▲ Mandatory Prerequisites: Internet must be reachable and DNS must resolve from your EVE Server. EVE ISO installation requires internet access and DNS to get updates and install the latest EVE-PRO version from the EVE-NG repository, to check it, do a named ping, for example ping www.google.com

Any existing EVE-NG Pro installation is already a EVE-NG "Master", cluster members will need to be installed as "Satellite" and can then easily be joined. Please refer Chapter 3

## 15.5 ESXi EVE Satellite VM installation


Download EVE-NG Professional ISO distribution image: <a href="https://www.eve-ng.net/index.php/download/">https://www.eve-ng.net/index.php/download/</a>


## 15.5.1 EVE-NG Satellite ESXi VM Setup and Settings


Step 1: Upload EVE ISO image to the ESXi store.	Step 2: Create NEW VM
-------------------------------------------------	-----------------------

© EVE-NG LTD Page 219 of 263











© EVE-NG LTD Page 220 of 263




Step 7: Set the size of HDD for your new EVE Satellite VM. It is recommended to set "Thick Provisioned eagerly provisioned". Server EVE HDD is recommended to set at least 500Gb



Step 8: Set your Management network. Adapter type VMXNET3



Step 9: Add new device to your EVE VM, CD/DVD



Step 10: Set DVD drive to "Datastore ISO File" and browse your uploaded EVE-PRO.iso. Make sure that Status is checked ON, "Connect at power on"



## 15.5.2 EVE-NG Satellite ESXi VM Installation steps

Mandatory Prerequisites: Internet must be reachable from your PC and VMware. EVE ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must work as well, to check it, do a named ping, for example ping www.google.com

#### Satellite EVE ESXi VM Installation from ISO has 3 Phases


#### Phase 1 (Ubuntu installation)

Step 1: Power ON EVE VM. Chose English and confirm with Enter.

Step 2: Be sure if "Install Eve Agent" is highlighted. Confirm with Enter.


© EVE-NG LTD Page 221 of 263







Step 3: Make sure if English is selected and confirm with Enter.




Step 4: You can select your own Location, or later, after management IP assignment, location will be set automatically. You can leave United States. Confirm with Enter



Step 5: Configure keyboard, select NO confirm with Enter.




Step 6: Leave United States. Confirm with Enter



© EVE-NG LTD Page 222 of 263



Step 7: Select English US confirm with Enter.




Step 8: **DHCP ENABLED**, EVEs hostname by default is **eve-ng**. You can change it if you wish. Using the Tab key select continue and confirm with Enter. Continue to **Step 15** 



Step 9: **DHCP DISABLED**/Static IP setup. If you have not enabled DHCP in the network, you must assign an IP address manually. Confirm Continue with Enter.



Step 10: Confirm selection "Configure network manually" with Enter



Step 11: Enter your desirable EVE management IP, using the Tab key select "Continue" and confirm with Enter

Step 12: Correct your subnet mask, using the Tab key select "Continue" and confirm with

© EVE-NG LTD Page 223 of 263





Step 13: Correct your Gateway IP, using the Tab key select "Continue" and confirm with Enter

The gateway is an IP address (four numbers secreted by periods) that indicates the sateway router, also known as the default noter. All traffic that sees outside your Law may have no router in intercent) is sent through this router. In rare circumstances, you may have no router in that case, you can leave this blank. If you don't know the proper arriver to this question, consult your network administrator.

Gateway:

[Station Stock

Grade Station Stock

Grade Station Stock

Grade Station Stock


Grade Station Statio

Step 14: IMPORTANT. Name server must respond to the Internet and will be used during the next install steps. Enter your name server IP. Using the Tab key select "Continue" and confirm with Enter

The name servers are used to look up host names on the network. Please enter the IP addresses (not host names) of up to 3 name servers, separated by spaces. Do not use commus. The first name server in the list will be the first to be queried. If you don't want to use any name server, just leave this field blank.

Name server addresses:

INDUSTRIBUTION OF THE PROPERTY OF THE P



Step 16: Enter your network domain name. You are free to use any, for example: **eve-ng.net** 

© EVE-NG LTD Page 224 of 263



Using the Tab key select continue and confirm with Enter

[1] Configure the network

The downin name is the part of your internet address to the right of your host name. It is often something that ends in .com, net, .edu. or ong. If you are setting up a home network, you can make something up, but make sure you use the same downin name on all your computers.

Commit name:

(So Back)

Step 17: If your DNS IP settings are correct, Ubuntu will detect your location from Internet. Confirm with Enter.



Step 18: Select Continue and confirm with Enter.



Step 19: Select **no automatic** updates and confirm with Enter. Security updates can be run later manually from EVE cli.

© EVE-NG LTD Page 225 of 263





## EVE Satellite VM Installation Phase 2 (EVE Satellite installation)

Step 20: Continue with Enter, the EVE VM will reboot and finish the installation phase 2



Step 21: Once EVE login screen appeared, login in CLI with root/eve and follow installation Phase 3



#### EVE Satellite VM Installation Phase 3 (Management IP setup and updates)

Step 19: Setup EVE Management IP address. A Static IP address setup is preferred

Follow steps in section 3.5.1 for static IP

Step 20: After your EVE is rebooted,

Login to EVE Satellite CLI and type:

apt update
apt upgrade

**NOTE:** To verify your EVE Satellite server installation type £dpkg -I eve-agent" it should display latest EVE Agent/Satellite version:

© EVE-NG LTD Page 226 of 263



**NOTE:** If your newly installed satellite shows nothing like above, you must check your internet reachability and verify DNS configuration on your Satellite server.

```
root@eve-sat01:~# ping www.google.com
PING www.google.com (172.217.22.164) 56(84) bytes of data.
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=1
ttl=120 time=8.84 ms
64 bytes from arn09s11-in-f164.1e100.net (172.217.22.164): icmp_seq=2
ttl=120 time=8.84 ms
^C
--- www.google.com ping statistics ---
2 packets transmitted, 2 received, 0% packet loss, time 1001ms
rtt min/avg/max/mdev = 8.848/8.848/8.849/0.094 ms
root@eve-sat1:~#
```

#### Launch Satellite installation manually

```
root@eve-sat01:~# cd /etc
root@eve-sat01:~# ./eve-setup
```

## 15.6 Bare metal server EVE Satellite installation

Download Ubuntu 18 Server ISO distribution image:

https://releases.ubuntu.com/18.04/ubuntu-18.04.5-live-server-amd64.iso

Mandatory Prerequisites: Internet must be reachable from your Server. This ISO installation requires internet access to get updates and install the latest EVE-PRO version from the EVE-NG repository. DNS must resolve names!

#### 15.6.1 Ubuntu Server Installation Phase 1




© EVE-NG LTD Page 227 of 263



Step 3: Make sure that English is selected and confirm Done with Enter



Step 4: It is strongly recommended to use Static IP address for bare metal server. Use Tab key and select ensXXX ethernet interface to edit, confirm with Enter



Step 5: Select "Edit IPv4", confirm with enter.

Network connections ( Heip ]

Configure at least one interface this server can use to talk to other machines, and which preferably provides sufficient access for updates.

Interface the provide of the provide of the provided that it is not the machines, and the provided that it is not the machines, and the provided that it is not that the provided that it is not that the provided that it is not that the provided that it is not the provided that it is not that the provided tha


Step 6: Hit Enter, to select IPv4 method. Use down arrow key to select Manual. Confirm with Enter



Step 7: Using Tab key fill your network settings. Select Save and confirm with Enter. The name server must be able to resolve public DNS entries!



Step 8: Using Tab key select "Done" and confirm with Enter



© EVE-NG LTD Page 228 of 263





Step 10: If your network and DNS is configured properly, Ubuntu install will offer ubuntu mirror address from closest source.

Continue with Enter.

Configure (bourts service sirror

If you use an alternative sirror for (bourts, enter its details here.

Mirror address: http://lv.anchive.ubunts.com/abunts

You say provide an archive sirror that sill be used instead of the default.

Step 11: Leave all default settings. Make sure is selected "Use entire disk" and "Set up this disk as LVM group". Unselected "Encrypt the LVM group with LUKS". Select Done and confirm with Enter.



Step 12: Verify your HDD setting, select Done and confirm with Enter



Step 13: Using Arrow down key select "Continue" and confirm with Enter



Step 14: Using the Tab key fill your user details, select Done and confirm with Enter



© EVE-NG LTD Page 229 of 263



Step 15: IMPORTANT: Using Spacebar key select "Install SSH OpenSSH server. Using the Tab key select "Done" and confirm with You can choose to install the OpenSSH server package to enable secure remote access to your server.

Step 16: Using Tab key select Done and confirm with Enter

Step 17: Wait till your server finish Ubuntu install. Using Tab key select Reboot Now and confirm with Enter

[ View full log ]

Step 18: Remove your installation media from server and confirm with Enter

nutabum. Journ the "live" preinstalled system cleanly... ng of LVM2 mirrors, snapshots etc. using dmeventd or progress polling.

Step 19: Use your previously created username and password to login in server. Example in this how steps was user/eve

Step 20: Login in the server as root:

```
sudo su
[sudo] password for user: eve
user@eve–ng:~$ sudo su
[sudo] password for user:
root@eve–ng:/home/user# cd
root@eve–ng:~# _
```

Page 230 of 263 © EVE-NG LTD



Step 21: Create root user password.

passwd root
Enter new UNIX password: eve
Retype new UNIX password: eve

root@eve–ng:~# passwd root Enter new UNIX password: Retype new UNIX password: passwd: password updated successfully root@eve–ng:~# \_ Step 22: Allow SSH access for root user.

nano /etc/ssh/sshd config

# Navigate with arrow down key to uncomment

PermitRootLogin prohibit-password
Change to

PermitRootLogin yes

To save edited sshd\_config use keys combo:

[Ctrl]+[o] Letter o (oscar)

Enter

[Ctrl]+[x] Letter x (x-ray) for exit

```
# Ciphers and keying
#Rekeyi.mit default none
# Losging
#SystogFacility AUTH
#Loglevel INFO
# Authentication:
#LoginGraceTime 2m
PermitRootLogin yes
#SystogFacility AUTH
#LoginGraceTime 2m
PermitRootLogin yes
#Bassachiniss
#Hassessions 10
#PubbesAuthentication yes
# Expect .ssh/authorized_keys2 to be disregarded by default in future.
#AuthorizedKeysFile .ssh/authorized_keys .ssh/authorized_keys2
#AuthorizedKeysFile none
#AuthorizedKeysCommand none
#AuthorizedKeysCommand none
#AuthorizedKeysCommandDiser nobody
# For this to work you will also need host keys in /etc/ssh/ssh_known_hosts
#HostbasedAuthentication no
```

Step 23: Restart SSH service on the server.

service sshd restart

Step 24. IMPORTANT: expand your server LVM partition to use all size of the HDD volume. Use Putty or other native terminal access as root to the server:

apt clean

lvextend -l +100%FREE /dev/ubuntu-vg/ubuntu-lv

resize2fs /dev/ubuntu-vg/ubuntu-lv

```
root@eve-ng:~#
root@eve-ng:~# lvextend -l +100%FREE /dev/ubuntu-vg/ubuntu-lv
Size of logical volume ubuntu-vg/ubuntu-lv changed from 149.50 GiB (38272 extents) to <299.00 GiB (76543 extents).
Logical volume ubuntu-vg/ubuntu-lv successfully resized.
root@eve-ng:~# resize2fs /dev/ubuntu-vg/ubuntu-lv
resize2fs l.44.1 (24-Mar-2018)
Filesystem at /dev/ubuntu-vg/ubuntu-lv is mounted on /; on-line resizing required
old_desc_blocks = 19, new_desc_blocks = 38
The filesystem on /dev/ubuntu-vg/ubuntu-lv is now 78380032 (4k) blocks long.
root@eve-ng:~#
```

root@eve-ng:"# df -h
Filesystem Size Used Avail Use% Mounted on udev 7.90 0 7.90 0% /dev
tmpfs 0 7.90 11M 1.60 11M 1.60 12M /run
/dev/mapper/ubuntu--vg-ubuntu--1v 2940 7.70 271 4% /
tmpfs 7.90 0 7.90 0% /dev/shm
tmpfs 5.0M 0 5.0M 0% /run/lock
tmpfs 7.90 0 7.90 0% /sys/fs/cgroup
/dev/sda2 976M 159M 750M 18% /boot
tmpfs 1.60 0 1.60 0% /run/user/0
root@eve-ng:"#

© EVE-NG LTD Page 231 of 263




# Step 25: IMPORTANT: Edit network interface name nano /etc/netplan/00-installer-config.yaml change interface name "ensXXX" to "eth0" To save edited 00-installer-config.yaml use keys combo: [Ctrl]+[o] Letter o (oscar) Enter [Ctrl]+[x] Letter x (x-ray) for exit Before: # This is the network config written by 'subiquity' network: ension: # This is the network config written by 'subiquity' network: ension: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the network config written by 'subiquity' network: # This is the net

Step 26: Update interface names with single line command:

```
sed -i -e 's/GRUB_CMDLINE_LINUX_DEFAULT=.*/GRUB_CMDLINE_LINUX_DEFAULT="net.ifnames=0
noquiet"/' /etc/default/grub
```

#### Step 27: Update GRUB

update-grub



#### 15.6.2 EVE Satellite Installation Phase 2

#### Step 30: Launch EVE-Satellite (agent) Internet installation

```
wget -O - https://www.eve-ng.net/repo-bionic/install-eve-agent.sh | bash -i
```

**Verification:** Verify your EVE-Satellite server installation, type "dpkg -I eve-agent" command, it must display latest EVE Satellite version

Step 31: Reboot EVE-Satellite (agent)

© EVE-NG LTD Page 232 of 263



reboot

Step 32: After your Satellite is rebooted, login to the Satellite CLI and type:


```
apt update
apt upgrade
```

## 15.7 Google Cloud EVE Satellite installation

## 15.7.1 Preparing Ubuntu boot disk template

Step 1: Navigate: Navigation Menu/Compute Engine/VM Instances

Step 2: Open the google cloud shell and press: "START CLOUD SHELL"



Step 3: create a nested Ubuntu 18.04 image model. Copy and paste the below command into the shell. Use copy/paste. crtl +c/ctrl +v. It is single line command (copy all command below in cli). Confirm with "enter":

gcloud compute images create nested-ubuntu-bionic --source-image-family=ubuntu-1804-lts --source-image-project=ubuntu-os-cloud --licenses https://www.googleapis.com/compute/v1/projects/vm-options/global/licenses/enable-vmx



You will get the following output when your image is ready:


© EVE-NG LTD Page 233 of 263





## 15.7.2 Creating VM

Step 1: Navigate: Navigation Menu/Compute Engine/VM Instances and press "Create"



Step 2: Assign the name for your VM


Step 3: Set your own region and zone

Step 4: Edit your Machine Configuration. General-Purpose. Choose the series of CPU platform, Preferred are *Intel CPUs Skylake or Cascade*.

Step 5: Choose your desirable CPU and RAM settings. IMPORTANT: "Deploy a container image" must be UNCHECKED.

© EVE-NG LTD Page 234 of 263






Step 6: Select Boot disk. Press Change




Step 7. Select Custom images and the *custom boot image you created previously*. Choose HDD disk type and size. HDD size can vary depends of your needs.

© EVE-NG LTD Page 235 of 263





## Step 7: Allow https traffic and create VM




## 15.7.3 EVE GCP Satellite installation

## Step 1: Connect to the VM with the first option "Open in browser window"



© EVE-NG LTD Page 236 of 263





Step 2: Launch installation with:

#### Type the below command to become root:

sudo -i

#### Start EVE-Satellite installation

wget -O - https://www.eve-ng.net/repo-bionic/install-eve-agent.sh | bash -i

#### Step 3: Update and upgrade your new EVE-Satellite

apt update

apt upgrade

Confirm with Y

#### Step 4. Reboot EVE. Allow some time for reboot and then press "Reconnect"

```
Sistering from the config file /stc/console-setup/compose.ISO-8859-1.inc ...


sv version of config file /stc/console-setup/compose.ISO-8859-13.inc ...

sv version of consistering file /stc/console-setup/compose.ISO-8859-13.inc ...

sv version of consistering from the standard from
```

## Step 5: VERY IMPORTANT: Setup IP

Once the IP wizard screen appears, press ctrl + c and type the below command to become root: sudo -i



Now follow the IP setup wizard, section: 3.5.2.

© EVE-NG LTD Page 237 of 263




#### **IMPORTANT**: set IP as DHCP!

Your EVE-Satellite public IP will be used for join satellite to the MASTER node.



#### 15.7.4 GCP Firewall rules for Cluster

Step 1: Navigate: Navigation menu/VPC Network/Firewall rules




Step 2: Create new firewall rule



Step 3: Create an ingress and egress FW rules; allow UDP ports all and TCP 22

© EVE-NG LTD Page 238 of 263






## 15.8 Cluster Management

#### 15.8.1 Join Satellite nodes to the Master

Step 1: Make sure that you have reachability between Master and Satellite nodes and firewall rules are configured in your network if FW is set between them. Firewall rules Section 15.2.1


Step 2: Navigate: System/Cluster Management





Step 3: Press Add Member and fill your Satellite details:

- Member's Name: use any suitable name for your satellite node
- IP address: Your satellite IP. In GCP version it will be public IP
- Member's Root Password: Your Satellite node password
- Press Add Member



© EVE-NG LTD Page 239 of 263



Step 4: After certain of time Satellite will join to the Master



#### 15.8.2 Remove Satellite nodes from the Master

Step 1: Navigate: System/Cluster Management

#### Step 2: Press Remove Member



## 15.8.3 Re-join Satellite nodes from the Master

Step 1: Navigate: System/Cluster Management

## Step 2: Press Remove Member



Step 3: Go to Satellite node CLI and rest IP address. It is necessary to refresh SSH key for rejoin Satellite to the Master.

CLI:

Login as root to the Satellite node and type:

```
rm -f /opt/ovf/.configured
su -
```

EVE Satellite will initiate IP setup wizard. Follow Section 3.5.1

Step 4: Join Satellite accordingly Section 15.8.1

## 15.8.4 Users assignment to the dedicated Satellite

Step 1: Navigate to Management/User Management



Step 2: Create or Edit existing user

© EVE-NG LTD Page 240 of 263





Step 3: Choose the Satellite to be assigned for this user.


Step 4. User will be locked and will use only selected Satellite node. Editor and User roles cannot change or choose other satellite members.



# 15.9 Creating EVE labs in Cluster

- Step 1: Create new or edit your existing lab
- Step 2: On lab Node right click/edit
- Step 3: Select preferred Satellite node and click save





Option to assign cluster nodes for single lab devices.

Lab Side bar/Nodes, column SATELLITE, Select your cluster satellites for devices in the lab.



© EVE-NG LTD Page 241 of 263



## 15.9.1 Master images synchronization with Satellites

Once you have assigned certain lab device to use cluster Satellite node and start it, the automatic rsync process is initiated from Master node copy necessary image to the Satellite cluster member. During rsync process between Master and Satellite lab device will display "Clock" sign beside device. After image rsync process is completed, Lab device will turn sign to "Play", running state.



Large size lab devices/images, rsync process can take some time. It depends of the network speed between the cluster members.


Once the image is copied into Satellite node, lab device will start immediately. RSYNC process initiates only once if particular device image does not exist on Satellite node.

## 15.10 Cluster system monitoring


## 15.10.1 Cluster Monitoring page

Navigate: System/Cluster Management Information columns displaying live information about cluster members utilization Satellite nodes have option to reboot or shutdown.

If the cluster is healthy and fully functional, the Status column will display "GREEN" dot beside the cluster members.



If the Satellite node is down or not reachable, the Status column will display "RED" dot



If the Satellite node is reachable but malfunctioning, Agent service is stopped or crashed, Status will be displayed as Yellow DOT. (stop/reboot possible)



© EVE-NG LTD Page 242 of 263




## 15.10.2 Satellite disaster recovery

Use case: If a satellite node crashed, was powered off while lab devices were running on it or the connection to the satellite was lost, the Master node will still have these nodes in a running state even if this is no longer the case.

To remediate this situation, you have to purge the local state information about the satellite before recovering the satellite, booting it back up or recovering the connection.

Step 1: To verify status of lab nodes:

Navigate Management/Nodes management. If you observing that crashed Satellite nodes are still alive and visible follow Step 2



Step 2. Navigate: System/Cluster Management

Use Purge Button to clean crashed Satellite devices from the Master.



Are you sure you want to remove all running consoles satellite 2?




## 15.10.3 EVE Cluster Status

Navigate: System/Cluster Management

© EVE-NG LTD Page 243 of 263





## 15.10.4 Cluster monitoring cli commands

#### On EVE Master:

Cluster System CLI Commands:

```
Check Cluster status:
```

## SSH to the Satellite node from the Master status:

```
ssh 172.29.130.<satId>
```

```
#####Example SSH to SAT1#####
root@eve-ng:~# ssh 172.29.130.1
Welcome to Ubuntu 18.04.5 LTS (GNU/Linux 4.20.17-eve-ng-uksm-wg+x86 64)
```

\* Documentation: https://help.ubuntu.com

\* Management: https://landscape.canonical.com \* Support: https://ubuntu.com/advantage

\* Canonical Livepatch is available for installation.

- Reduce system reboots and improve kernel security. Activate at: https://ubuntu.com/livepatch

Last login: Sun Jan 31 22:24:06 2021 from 10.6.6.14

root@eve-sat1:~#

# 15.11 Cluster system upgrade

Pre-requisites: The Master node must reach internet and resolve DNS.

On the EVE Master CLI run commands:

© EVE-NG LTD Page 244 of 263



apt update
apt upgrade

The cluster Satellites will upgrade automatically with EVE master. There no need any extra upgrade run for Satellite nodes.

## To update manually Satellite nodes from Master EVE:

```
root@eve-ng:~# unl_wrapper -a updatesat

Feb 01 00:03:24 Feb 01 00:03:24 Online Check state: Valid
Feb 01 00:03:24 update sat 1
ii eve-agent    3.0.1-71    amd64    Agent for EVE-NG Sat
Cluster member
Feb 01 00:03:24 update sat 2
ii eve-agent    3.0.1-71    amd64    Agent for EVE-NG Sat
Cluster member
root@eve-ng:~#
```

© EVE-NG LTD Page 245 of 263



# 16 EVE Troubleshooting

# 16.1 CLI diagnostic information display commands

16.1.1 Display full EVE Pro diagnostic

```
eve-info
```

16.1.2 Display the currently installed EVE Pro version:

dpkg -l eve-ng-pro

16.1.3 Display if EVEs Intel VT-x/EPT option on/off:

kvm-ok

```
root@eve-ng:~# kvm-ok
INFO: /dev.kvm exists
KVM acceleration can be used
root@eve-ng:~#
```

16.1.4 Display EVEs CPU INFO:

lscpu

16.1.5 Display EVEs CPU manufacturer:

lsmod | grep ^kvm

```
root@eve-ng:~# lsmod | grep ^kvm_
kvm_intel 212992 74
root@eve-ng:~#
```

© EVE-NG LTD Page 246 of 263



## 16.1.6 Display EVEs HDD utilization.

If the /boot only has a little space left you can refer to section **Error! Reference source not found.** If the eve—ng—vg—root reaches 99% or 100% then you will need to expand the HDD in order to continue using EVE. The Solution to expand your HDD is described in section 16.1

df -h

```
root@eve-ng:~# df -h
Filesystem Size Used Avall Use% Mounted on udev tmpfs 7,90 52M 7.90 1% /run
/dev/mapper/eve--ng--vg-root 6810 3700 2830 57% /
tmpfs 400 0 400 0% /dev/shm
tmpfs 5.0M 0 5.0M 0% /run/lock
tmpfs 400 0 400 0% /sys/fs/cgroup
/dev/sdal 472M 83M 365M 19% /boot
```

## 16.1.7 Display EVEs Bridge interface status

```
brctl show
```

```
        root@eve-ng:"#
        brctl show
        STP enabled docker0
        interfaces

        docker0
        8000.0242c0db8435
        no
        enabled

        nat0
        8000.000000000000
        no
        eth0

        pnet0
        8000.000c29d0aa94
        no
        eth1

        pnet1
        8000.000c29d0aabc
        no
        eth1

        pnet2
        8000.000c29d0aabe
        no
        eth2

        pnet3
        8000.000c29d0aabe
        no
        eth3

        pnet4
        8000.000c29d0aabe
        no
        eth4

        pnet5
        8000.00000000000
        no
        eth4

        pnet6
        8000.00000000000
        no
        pnet7

        pnet7
        8000.00000000000
        no
        pnet8

        8000.000000000000
        no
        pnet9
        8000.00000000000
```

## 16.1.8 Display EVEs system services status

```
systemctl list-unit-files --state=enabled
```

## 16.2 Expand EVEs System HDD


▲ IMPORTANT NOTE: DO NOT expand your current/existing HDD on your EVE VM!

© EVE-NG LTD Page 247 of 263




## 16.2.1 HDD space alert

**Important:** by default, EVE will trigger alerts if there are 3GB or less HDD space available. Additional nodes will not start until more space is added or freed up. A link is provided in the notification bubble on how to properly add an additional HDD.



To edit HDD space threshold for the alert is customizable. please follow section: 7.4.1



#### 16.2.2 Expand HDD on VMware Workstation

Expanding your EVEs system HDD is achieved by adding an additional HDD to your EVE VM.

Step 1: Stop all your labs and shutdown EVE.

Use EVE CLI command: shutdown -h now

Step 2: Go to edit VM settings and add a new Hard drive. Then click Next.


Step 3: Leave the recommended SCSI HDD option and then click Next

Step 4: Make sure you have selected the option "Create a new Virtual disk."



Step 6: Make sure you have set the option "Store Virtual disk as a single file" and then click Next

Step 7: Optional: Specify the location of where your new HDD will be stored, then click Finish.



© EVE-NG LTD Page 248 of 263



Step 8: Boot your EVE VM, HDD size will be expanded automatically. To verify, use the command to verify HDD utilization referenced in section 16.1.5

## 16.2.3 Expand your HDD on ESXi

Expanding your EVEs system HDD is achieved by adding an additional HDD to your EVE VM.

Step 1: Stop all your labs and shutdown EVE.

Use EVE CLI command: shutdown -h now

Step 2: Go to edit VM settings and add a new Hard drive. Then click Next

Step 3: Make sure you have selected the option "Create a new Virtual disk." Then click Next

Step 4: Set your desirable HDD Size; example 200GB.



Step 6: Specify the location of where your new HDD will be stored and then click Next

Step 7: Leave the recommended SCSI HDD option as is and click Finish.

Step 8: Boot your EVE VM, the HDD size will be expanded automatically. To verify, use the command to verify HDD utilization referenced in section 16.1.5

#### 16.2.4 Expand your HDD on a Bare Metal EVE Server

It is a complicated process to expand a HDD for a bare metal EVE server. Please open a ticket in our Live chat support for advice.

https://www.eve-ng.net/index.php/live-helpdesk/

Use a google account to join in the Live Chat or create new chat account.

# 16.3 Reset Management IP

Type the following commands into the CLI followed by enter:


rm -f /opt/ovf/.configured
su -

http://www.eve-ng.net/documentation/installation/bare-installIP address setup wizard. Please follow the steps in section 3.5.1 for Static IP or 3.5.2 for DHCP IP setup.

# 16.4EVE PRO SQL Database recovery

Starting EVE PRO version 3.0.1-21 and later, you can recover SQL user database in case of disaster:

© EVE-NG LTD Page 249 of 263





unl wrapper -a restoredb

Below is SINGLE LINE Command to restore SQL Database.

unl\_wrapper -a restoredb ; grep -q default\_time\_zone
/etc/mysql/mysql.conf.d/mysqld.cnf || echo
"default\_time\_zone='+00:00'" >> /etc/mysql/mysql.conf.d/mysqld.cnf ;
systemctl restart mysql

## 16.5 EVE PRO Migration from host to host

Step 1: On newly installed EVE navigate to:

#### cd /opt/unetlab/scripts

Step 2: Run migration script migrate.sh where source IP is your old EVE host IP and root password of old EVE. [./migrate.sh -s <old eve ip> -p <root password>]

Example:


```
root@eve-ng:/opt/unetlab/scripts# ./migrate.sh -s 192.168.1.100 -p eve
```

Step 3: After migration is completed, deactivate EVE license on old host, and load license in the new EVE machine.


https://www.eve-ng.net/index.php/documentation/howtos/recover-rehosting-eve-ng/

## 16.6 EVE Log files

EVE log Files can be obtained from the System Logs page under the System dropdown menu



Use the menu to collect log file data you are interested in.



# 16.7 EVE cli diagnostic info

Use EVE cli to obtain your EVE information:

© EVE-NG LTD Page 250 of 263



eve-info

© EVE-NG LTD Page 251 of 263



## 17 EVE Extras

## 17.1 EVE Pro Radius server setup for user authentication

▲ Mandatory Prerequisites: Updated EVE-PRO version 2.0.6-1 or later.

Please follow section: 7.4.1


Ticaco Tollow Coc			
System settings			
Radius Server #1	IP	Port	Secret
	0.0.0.0	1812	•••••
Radius Server #2	IP	Port	Secret
	0.0.0.0	1812	*****

## 17.1.1 EVE User setup for Radius authentication


Step 1: Open the User management submenu. Management>User management and click Add user

Step 2: The Add New User management window will pop up. Fill in the main information about your EVE user. Make sure that you're the username of the account created in EVE matches with the Radius server database.

Step 3: Enable the External Auth (Radius) checkbox. Any existing password will be removed, because the authenticator will check with the Radius server for credentials.



Step 4: If you have purchased licenses for different EVE user roles, you can choose the preferred user role. For licensing and user roles please refer to section 4




Step 5: Set the access date and time From - to. If the fields are left empty (untouched), your user will have no time restrictions for accessing the EVE Server. Account validity with time settings is available for Editor and User roles only.

© EVE-NG LTD Page 252 of 263



Admin accounts have no time limit for account validity, and Account Validity time cannot be set.




Step 6: The POD number is a value assigned to user accounts automatically. POD numbers are like user profiles inside of EVE and are a unique value for every user Think of PODs like a virtual rack of equipment for each user. Admins can assign a preferred number between 1-128. Please keep POD numbers unique between users!



Step 8. The username created inside EVE must match the username on the Radius server

**Example:** EVE user authenticated with ISE 2.1 Radius server.



## 17.2 Lab Chat




© EVE-NG LTD Page 253 of 263




## 17.3 Custom MAC address for node management

**NOTE:** Custom first MAC is supported for Qemu nodes only.

Qemu nodes has option to change first interface MAC address.





# 17.4 Windows node settings for Wifi dongle

Using a Wifi USB dongle, you can connect a WiFi-adapter to windows host inside EVE.

Step 1. Connect your USB Wifi dongle to your EVE server.

Step 2. Issue the following command on the EVE CLI to obtain BUS and host numbers which your USB WiFi is connected to:

lsusb

© EVE-NG LTD Page 254 of 263



```
root@eve-ng:~# lsusb

Bus 002 Device 002: ID 0cf3:9271 Atheros Communications, Inc. AR9271 802.11n

Bus 002 Device 001: ID 1d6b:0002 Linux Foundation 2.0 root hub

Bus 006 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub

Bus 005 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub

Bus 001 Device 003: ID 0424:2514 Standard Microsystems Corp. USB 2.0 Hub

Bus 001 Device 001: ID 1d6b:0002 Linux Foundation 2.0 root hub

Bus 004 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub

Bus 003 Device 001: ID 04e6:5116 SCM Microsystems, Inc. SCR331-LC1 / SCR3310 Sma

rtCard Reader

Bus 003 Device 001: ID 1d6b:0001 Linux Foundation 1.1 root hub

root@eve-ng:~#
```

Step 3. Add the windows node onto the topology and edit the Qemu line:

Change the type value:

#### type=q35

Add a comma and then the following line:

if=virtio -usb -device usb-host,hostbus=2,hostaddr=2


Where hostbus is your Bus value and hostaddr is your Device ID as seen in the figure above.

Full Windows host gemu line will look like this:

```
-machine type=q35,accel=kvm -cpu
host,+pcid,+kvm_pv_unhalt,+kvm_pv_eoi,hv_spinlocks=0x1fff,hv_vapic,hv
_time,hv_reset,hv_vpindex,hv_runtime,hv_relaxed,hv_synic,hv_stimer -
vga std -usbdevice tablet -boot order=cd -drive
file=/opt/qemu/share/qemu/virtio-win-
drivers.img,index=1,if=floppy,readonly,if=virtio -usb -device usb-
host,hostbus=2,hostaddr=2
```

© EVE-NG LTD Page 255 of 263





© EVE-NG LTD Page 256 of 263



# 18 Images for EVE

Images must be uploaded and prepared before they can be used in labs. The best way to upload images is to use the WinSCP tool for Windows environment or FileZilla for MAC OSX and Linux.

Link to download WinSCP:

https://winscp.net/eng/download.php

Link to download FileZilla:

https://filezilla-project.org/

To access EVE, use SSH protocol (port 22).

Supported images for EVE are stored in the three locations:

- IOL (IOS on Linux), /opt/unetlab/addons/iol/bin/
- Dynamips images, /opt/unetlab/addons/dynamips
- Qemu images, /opt/unetlab/addons/gemu

## 18.1 Qemu image naming table

▲ IMPORTANT NOTE: Intel VT-X/EPT must be enabled to run Qemu nodes in EVE. For information on how to enable this option, Refer to section 3: EVE Installation.

The directory names used for QEMU images are very sensitive and must match the table below exactly in order to work.

Ensure your image folder name starts as per the table. After the "-" you can add whatever you like to label the image. We recommend using the version of your image.

Folder name examples:

firepower6-FTD-6.2.1 acs-5.8.1.4

The image hdd inside the folder must be named correctly:

Example: hda.qcow2 or virtioa.qcow2

Full path Example: opt/unetlab/addons/qemu/acs-5.8.1.4/hda.qcow2

The table of proper folder names is provided in our website:

https://www.eve-ng.net/index.php/documentation/qemu-image-namings/

Supported HDD formats and Qemu versions for the EVE images:

HDD Format	HDD name example	
lsi([a-z]+).qcow	lsia.qcow	
hd([a-z]+).qcow	hda.qcow	
virtide([a-z]+).qcow	virtidea.qcow	

© EVE-NG LTD Page 257 of 263



virtio([a-z]+).qcow	virtioa.qcow
scsi([a-z]+).qcow	scsia.qcow
sata([a-z]+).qcow	sataa.qcow

Supperted Gemu Versions	okbook
	ion 4.5
2.0.2	
2.2.0	
2.4.0	
2.5.0	
2.6.2	
2.12.0	
3.1.0	
4.1.0	

## 18.2 How to prepare images for EVE

How to add EVE-NG images please refer to:

https://www.eve-ng.net/index.php/documentation/howtos/

## 18.3 How to add custom image template

⚠ IMPORTANT NOTE: Upgrade from EVE version 2.0.5-XX to 2.0.6.-XX automatically will convert old config.php to new yml formats: If you had already custom templates in old php format, these templates will be automatically converted to custom\_templates.yml file during the upgrade process!

## 18.3.1 Templates folder choice

⚠ IMPORTANT NOTE: Starting from EVE-PRO Version 2.0.6-42, EVE installation is autodetecting what kind of CPU manufacturer has your server: Intel or AMD, to choose proper templates set. You can check it manually on EVE cli: example below, showing that EVE has Intel CPU.

- If you have Intel CPU, then your template files are in "/opt/unetlab/html/templates/intel/"
- If you have AMD CPU, then your template files are in "/opt/unetlab/html/templates/amd/"

#### 18.3.2 Prepare template file

NOTE: For templates development use templates folder which is matching your EVE server CPU.


Example below will be based for Intel CPU EVE custom image template. Use EVE cli or WinSCP/Filezilla to create template.

Step 1: Navigate to EVE location: /opt/unetlab/html/templates/intel/

Step 2: Choose your most suitable template from which you want to make copy and create own image template. (example: newimage.yml)

© EVE-NG LTD Page 258 of 263





Step 3: Make a copy from source template newimage.yml. Example: Using CLI create template and name it ngips.yml.

```
cp /opt/unetlab/html/templates/intel/newimage.yml /opt/unetlab/html/templates/intel/ngips.yml
```

You can create new template using WinSCP or Filezilla as well.

```
root@eve-ng:"# cp /opt/unetlab/html/templates/intel/newimage.yml /opt/un
```

**IMPORTANT**: The new name of your template will be related to your image foldername. Your image foldername must start with prefix "ngips-"

Example: image foldername under /opt/unetlab/addons/qemu/ngips-6.5.0-115

```
root@eve-ng:~# cd /opt/unetlab/addons/qemu/
root@eve-ng:/opt/unetlab/addons/qemu# ls
al0-VThunder-4.1.4 ise-2.6.0.156.SPA-L
ampcloud-2.3.5-L junipervrr-19.2R1-52.2
ampcloud-3.0.2 kerio-control-9.3.2
linux-mint-18.3-cinnamon-64bit
linux-slax-64bit-9.3.0
linux-slax-64bit-9.3.0
linux-slax-64bit-9.3.0.tar.gz
mikrotik-6.44.5
asav-9131-100 nsvpx-12.0.53.13
```

## 18.3.3 Prepare interface format and name lines

EVE Pro has included option to create various interface names, sequences and numbering. Please refer table below.

Formula	Template line format example	Will produce
eth_format: <pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	eth_format: Gi{1}/{0-8}	Gi1/0 Gi1/1 Gi1/2 Gi1/3 Gi1/4 Gi1/5 Gi1/6 Gi1/7

© EVE-NG LTD Page 259 of 263



		Gi2/0 Gi2/1
eth_format: <pre>cth_format: <pre>cth_fo</pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre>	eth_format: Ge{0}/{0-4}	Ge0/0 Ge0/1 Ge0/2 Ge0/3 Ge1/0 Ge1/2 Ge1/3 Ge2/0 Ge2/1 Ge2/2
eth_format: <prefix>{<first value="">}</first></prefix>	eth_format: Gi{0}	Gi0 Gi1 Gi2 Gi3
eth_format: <prefix>{<first value="">}</first></prefix>	eth_format: G0/{0}	G0/0 G0/1 G0/2 G0/3
eth_name: <pre><pre><pre>cth_name</pre></pre></pre>	eth_name: - M1 - T1 - T2	M1 T1 T2
eth_name: <pre><pre><pre><pre>eth_name</pre></pre></pre></pre>	eth_name: - MGMT - DATA - TRAFFIC	MGMT DATA TRAFFIC

Combined first named interface following by formatted interfaces Example: We have to set first node interface name "eth0/mgmt" and next following interfaces must start from eth1 and change sequence accordingly. eth1, eth2,....,ethx


As your node first interface will be custom named (eth0/mgmt), therefore in the template "eth\_name:" must be added before "eth\_format:"

```
eth_name:
    eth0/mgmt
eth_format: eth{1}
```

This adding will produce Node interfaces.

© EVE-NG LTD Page 260 of 263





## 18.3.4 Edit your new template file:

For edit newly created template you can use WinSCP, FileZilla or cli. Example below shows template edit using cli and *nano* editor

```
cd /opt/unetlab/html/templates/intel/
nano ngips.yml
```

Change content, setting for various images can vary depends of vendor requirements. The interface name lines please refer Section: 18.3.2

```
# Copyright (c) 2016, Andrea Dainese
# Copyright (c) 2018, Alain Degreffe
 All rights reserved.
 Redistribution and use in source and binary forms, with or without
 modification, are permitted provided that the following conditions are met:
      * Redistributions of source code must retain the above copyright
       notice, this list of conditions and the following disclaimer.
      * Redistributions in binary form must reproduce the above copyright
       notice, this list of conditions and the following disclaimer in the
       documentation and/or other materials provided with the distribution.
      * Neither the name of the UNetLab Ltd nor the name of EVE-NG Ltd nor the
       names of its contributors may be used to endorse or promote products
       derived from this software without specific prior written permission.
# THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND
 ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED
 WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE
# DISCLAIMED. IN NO EVENT SHALL <COPYRIGHT HOLDER> BE LIABLE FOR ANY
# DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES
 (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES;
 LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND
# ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
 (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
# SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.
                                    \bigcirc
description: Cisco FirePower NGIPS
                                   → Node list name
cpulimit: 1
                                             ADD A NEW NODE
icon: IPS.png
cpu: 4
ram: 8192
ethernet: 3
eth name:
 eth0/mgmt
eth_format: eth{1}
```

© EVE-NG LTD Page 261 of 263



**Note:** Qemu options in the line may vary per image requirements. Please check manufacturer advice how to run KVM image

## 18.3.5 Prepare new icon for your template:

**Step 1** Use Filezilla or Winscp to copy your custom icon IPS.png (icon filename IPS.png used in ngips.yml)

This icon should be about 30-60 x 30-60 in the png format (switch.png is for example 65 x 33, 8-bit/color RGBA)

Step 2 Copy this new icon into /opt/unetlab/html/images/icons/

## 18.3.6 Template use

Step 1 Create directory /opt/unetlab/addons/qemu/ngips-6.5.0-115

```
mkdir /opt/unetlab/addons/qemu/ngips-6.5.0-115
```

Step 2 Upload image NGIPS, Refer Section: 0

# 18.4 How to hide unused images in the node list

Please follow section 7.4.1 or 8.1.1.1

© EVE-NG LTD Page 262 of 263



## 19EVE Resources

For additional updated information please follow our web site: https://www.eve-ng.net

How to updates: <a href="https://www.eve-ng.net/index.php/documentation/howtos/">https://www.eve-ng.net/index.php/documentation/howtos/</a>

How to videos: https://www.eve-ng.net/index.php/documentation/howtos-video/

https://www.eve-ng.net/index.php/documentation/knox-hutchinson-videos/

FAQ: https://www.eve-ng.net/index.php/faq/

Live support chat: <a href="https://www.eve-ng.net/index.php/live-helpdesk/">https://www.eve-ng.net/index.php/live-helpdesk/</a>

For access to live chat use your Google account or create new chat account.

EVE forum: https://www.eve-ng.net/forum/

To access forum resources, please create a new forum account.

EVE YouTube channel:

https://www.youtube.com/playlist?list=PLF8yvsYkPZQ0myW7aVMZ80k8FU04UUgjV

EVE Professional downloads: https://www.eve-ng.net/index.php/download/

EVE Community version downloads, free: <a href="https://www.eve-ng.net/index.php/community/">https://www.eve-ng.net/index.php/community/</a>

EVE Supported images: https://www.eve-ng.net/index.php/documentation/supported-images/

© EVE-NG LTD Page 263 of 263